



# **QGIS Server 3.22 User Guide**

**QGIS Project**

**2023 年 12 月 04 日**



# 目次

第 1 章	はじめに	1
第 2 章	はじめに	3
2.1	Debian のベースのシステムへのインストール	3
2.1.1	Apache HTTP Server	4
2.1.2	NGINX HTTP Server	7
2.1.3	Xvfb	12
2.2	Installation on Windows	14
2.3	Serve a project	16
2.4	Configure your project	17
2.4.1	WMS 機能	19
2.4.2	WFS 機能	20
2.4.3	WCS 機能	20
2.4.4	OWS を微調整する	20
2.5	Integration with third parties	20
2.5.1	Integration with QGIS Desktop	21
2.5.2	Integration with MapProxy	21
2.5.3	Integration with QWC2	21
第 3 章	サービス	23
3.1	Basics	23
3.1.1	SERVICE	24
3.1.2	REQUEST	24
3.1.3	MAP	24
3.1.4	FILE_NAME	25
3.1.5	Short name	25
3.2	Web 地図サービス (WMS)	26
3.2.1	GetCapabilities	27
3.2.2	GetMap	27
3.2.3	GetFeatureInfo	36
3.2.4	GetLegendGraphics	41
3.2.5	GetStyle(s)	56
3.2.6	DescribeLayer	57
3.2.7	GetPrint	58
3.2.8	GetProjectSettings	61
3.2.9	GetSchemaExtension	62
3.2.10	External WMS layers	62
3.2.11	Redlining	63
3.3	Web Feature Service (WFS)	66
3.3.1	GetCapabilities	66

3.3.2	GetFeature . . . . .	67
3.3.3	DescribeFeatureType . . . . .	75
3.3.4	Transaction . . . . .	76
3.4	Web Coverage Service (WCS) . . . . .	78
3.4.1	GetCapabilities . . . . .	79
3.4.2	DescribeCoverage . . . . .	80
3.4.3	GetCoverage . . . . .	82
3.5	Web Map Tile Service (WMTS) . . . . .	84
3.5.1	GetCapabilities . . . . .	84
3.5.2	GetTile . . . . .	85
3.5.3	GetFeatureInfo . . . . .	86
3.6	OGC API Features . . . . .	88
3.6.1	Resource representation . . . . .	89
3.6.2	Endpoints . . . . .	89
3.6.3	Pagination . . . . .	93
3.6.4	地物フィルタリング . . . . .	93
3.6.5	Feature sorting . . . . .	95
3.6.6	Attribute selection . . . . .	95
3.6.7	Customize the HTML pages . . . . .	96
<b>第 4 章</b>	<b>Catalog</b>	<b>99</b>
<b>第 5 章</b>	<b>プラグイン</b>	<b>103</b>
5.1	List of plugins . . . . .	103
5.2	Location of plugins . . . . .	103
5.3	インストール . . . . .	103
5.3.1	Manually with a ZIP . . . . .	103
5.3.2	With a command line tool . . . . .	104
5.4	HTTP サーバー構成 . . . . .	105
5.4.1	Apache . . . . .	105
5.5	プラグインの使用方法 . . . . .	105
<b>第 6 章</b>	<b>高度な構成</b>	<b>107</b>
6.1	ログを記録する . . . . .	107
6.2	環境変数 . . . . .	107
6.3	Settings summary . . . . .	109
6.4	サービスファイルへの接続 . . . . .	110
6.5	お使いの Linux サーバーにフォントを追加 . . . . .	110
<b>第 7 章</b>	<b>Development Server</b>	<b>113</b>
<b>第 8 章</b>	<b>コンテナ化された配備</b>	<b>115</b>
8.1	Simple docker images . . . . .	115
8.1.1	First run . . . . .	117
8.1.2	Usable sample . . . . .	118
8.1.3	Cleanup . . . . .	119
8.2	Docker stacks . . . . .	119
8.2.1	Swarm/docker-compose . . . . .	119

8.2.2	Kubernetes . . . . .	120
8.3	Cloud deployment . . . . .	125
8.3.1	AWS usecase . . . . .	125
<b>第 9 章</b>	<b>Frequently Asked Question</b>	<b>127</b>



# 第1章 はじめに

QGIS Server is an open source WMS, WFS, OGC API for Features 1.0 (WFS3) and WCS implementation that, in addition, implements advanced cartographic features for thematic mapping. QGIS Server is a FastCGI/CGI (Common Gateway Interface) application written in C++ that works together with a web server (e.g., Apache, Nginx). It has Python plugin support allowing for fast and efficient development and deployment of new features.

QGIS サーバーは、GIS ロジックのためのバックエンドとして、地図のレンダリングに QGIS を使用しています。また、Qt ライブラリは、グラフィックスおよびプラットフォームに依存しない C++ プログラミングのために使用されます。他の WMS のソフトウェアとは対照的に、QGIS サーバーは、サーバーの構成およびユーザー定義の地図作成ルールの間、設定言語として地図作成規則を使用します。

QGIS のデスクトップと QGIS サーバーは同じ可視化ライブラリを使用するように、ウェブ上で公開されている地図は、デスクトップ GIS と同じに見えます。

次のセクションでは、Linux (Debian、Ubuntu および派生物) と Windows に QGIS サーバをセットアップするためのサンプル構成を提供します。サーバプラグイン開発の詳細は `server_plugins` を参照。

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.

A copy of the license is included in the section `gnu_fdl`.



## 第2章 はじめに

### 2.1 Debian のベースのシステムへのインストール

We will give a short and simple installation how-to for a minimal working configuration on Debian based systems (including Ubuntu and derivatives). However, many other distributions and OSs provide packages for QGIS Server.

---

**注釈:** In Ubuntu you can use your regular user, prepending `sudo` to commands requiring admin permissions. In Debian you can work as admin (root), without using `sudo`.

---

Requirements and steps to add official QGIS repositories to install QGIS Server on a Debian based system are provided in [QGIS installers page](#). You may want to install at least the latest Long Term Release.

Once the target version repository is configured and QGIS Server installed, you can test the installation with:

```
/usr/lib/cgi-bin/qgis_mapserv.fcgi
```

If you get the following output, the server is correctly installed.

---

**注釈:** Depending on the version of QGIS, you might see slightly different output reported when you run `qgis_mapserv.fcgi`.

---

```
QFSFileEngine::open: No file name specified
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver JP2ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver JP2ECW to unload from GDAL_SKIP environment variable.
Content-Length: 206
Content-Type: text/xml; charset=utf-8

<ServiceExceptionReport version="1.3.0" xmlns="https://www.opengis.net/ogc">
  <ServiceException code="Service configuration error">Service unknown or unsupported</
  ↳ServiceException>
</ServiceExceptionReport>
```

---

**注釈:** As seen below, QGIS reports a Status 400 code, which correctly identifies the request has failed because

there is no active http session. This is not a bug and indicates the server is functioning properly.

---

```
Application path not initialized
Application path not initialized
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver JP2ECW to unload from GDAL_SKIP environment variable.
>Loading native module /usr/lib/qgis/server/libdummy.so"
>Loading native module /usr/lib/qgis/server/liblandingpage.so"
>Loading native module /usr/lib/qgis/server/libwcs.so"
>Loading native module /usr/lib/qgis/server/libwfs.so"
>Loading native module /usr/lib/qgis/server/libwfs3.so"
>Loading native module /usr/lib/qgis/server/libwms.so"
>Loading native module /usr/lib/qgis/server/libwmts.so"
QFSFileEngine::open: No file name specified
Content-Length: 102
Content-Type: application/json
Server: QGIS FCGI server - QGIS version 3.22.6-Białowieża
Status: 400
[{"code":"Bad request error","description":"Requested URI does not match any
↳registered API handler"}]
```

Let's add a sample project. You can use your own, or one from [Training demo data](#):

```
mkdir /home/qgis/projects/
cd /home/qgis/projects/
wget https://github.com/qgis/QGIS-Training-Data/archive/release_3.22.zip
unzip release_3.22.zip
mv QGIS-Training-Data-release_3.22/exercise_data/qgis-server-tutorial-data/world.qgs .
mv QGIS-Training-Data-release_3.22/exercise_data/qgis-server-tutorial-data/
↳naturalearth.sqlite .
```

Of course, you can use your favorite GIS software to open this file and take a look at the configuration and available layers.

To properly deploy QGIS server you need a HTTP server. Recommended choices are [Apache](#) or [NGINX](#).

### 2.1.1 Apache HTTP Server

---

注釈: In the following, please replace `qgis.demo` with the name or IP address of your server.

---

1. Install Apache and `mod_fcgid`:

```
apt install apache2 libapache2-mod-fcgid
```

2. You can run QGIS Server on your default website, but let's configure a `virtualhost` specifically for this, as follows.

1. In the `/etc/apache2/sites-available` directory, create a file called `qgis.demo.conf`, with this content:

```
<VirtualHost *:80>
  ServerAdmin webmaster@localhost
  ServerName qgis.demo

  DocumentRoot /var/www/html

  # Apache logs (different than QGIS Server log)
  ErrorLog ${APACHE_LOG_DIR}/qgis.demo.error.log
  CustomLog ${APACHE_LOG_DIR}/qgis.demo.access.log combined

  # Longer timeout for WPS... default = 40
  FcgidIOTimeout 120

  FcgidInitialEnv LC_ALL "en_US.UTF-8"
  FcgidInitialEnv PYTHONIOENCODING UTF-8
  FcgidInitialEnv LANG "en_US.UTF-8"

  # QGIS log
  FcgidInitialEnv QGIS_SERVER_LOG_STDERR 1
  FcgidInitialEnv QGIS_SERVER_LOG_LEVEL 0

  # default QGIS project
  SetEnv QGIS_PROJECT_FILE /home/qgis/projects/world.qgs

  # QGIS_AUTH_DB_DIR_PATH must lead to a directory writeable by the Server's
  ↳FCGI process user
  FcgidInitialEnv QGIS_AUTH_DB_DIR_PATH "/home/qgis/qgisserverdb/"
  FcgidInitialEnv QGIS_AUTH_PASSWORD_FILE "/home/qgis/qgisserverdb/qgis-auth.
  ↳db"

  # Set pg access via pg_service file
  SetEnv PGSERVICEFILE /home/qgis/.pg_service.conf
  FcgidInitialEnv PGPASSFILE "/home/qgis/.pgpass"

  # if qgis-server is installed from packages in debian based distros this
  ↳is usually /usr/lib/cgi-bin/
  # run "locate qgis_mapserv.fcgi" if you don't know where qgis_mapserv.fcgi
  ↳is
```

(次のページに続く)

```

ScriptAlias /cgi-bin/ /usr/lib/cgi-bin/
<Directory "/usr/lib/cgi-bin/">
    AllowOverride None
    Options +ExecCGI -MultiViews -SymLinksIfOwnerMatch
    Require all granted
</Directory>

<IfModule mod_fcgid.c>
    FcgidMaxRequestLen 26214400
    FcgidConnectTimeout 60
</IfModule>

</VirtualHost>

```

注釈: Some of the above configuration options are explained in the Server *environment variables* and *pg\_service* file sections.

- Let's now create the directories that will store the QGIS Server logs and the authentication database:

```

mkdir -p /var/log/qgis/
chown www-data:www-data /var/log/qgis
mkdir -p /home/qgis/qgisserverdb
chown www-data:www-data /home/qgis/qgisserverdb

```

注釈: *www-data* is the Apache user on Debian based systems and we need Apache to have access to those locations or files. The `chown www-data...` commands change the owner of the respective directories and files to *www-data*.

- We can now enable the virtual host and the `fcgid` mod if it's not already done:

```

a2enmod fcgid
a2ensite qgis.demo

```

- Now restart Apache for the new configuration to be taken into account:

```

systemctl restart apache2

```

- Now that Apache knows that he should answer requests to `http://qgis.demo` we also need to setup the client system so that it knows who `qgis.demo` is. We do that by adding `127.0.0.1 qgis.demo` in the `hosts` file.

```

# Replace 127.0.0.1 with the IP of your server.
sh -c "echo '127.0.0.1 qgis.demo' >> /etc/hosts"

```

**重要:** Remember that both the `qgis.demo.conf` and `/etc/hosts` files should be configured for your setup to work. You can also test the access to your QGIS Server from other clients on the network (e.g. Windows or macos machines) by going to their `/etc/hosts` file and point the `qgis.demo` name to whatever IP the server machine has on the network (not `127.0.0.1` as it is the local IP, only accessible from the local machine). On \*nix machines the hosts file is located in `/etc`, while on Windows it's under the `C:\Windows\System32\drivers\etc` directory. Under Windows you need to start your text editor with administrator privileges before opening the hosts file.

QGIS Server is now available at <http://qgis.demo>. To check, type in a browser, as in the simple case:

```
http://qgis.demo/cgi-bin/qgis_mapserv.fcgi?SERVICE=WMS&VERSION=1.3.0&
↔REQUEST=GetCapabilities
```

## 2.1.2 NGINX HTTP Server

**注釈:** In the following, please replace `qgis.demo` with the name or IP address of your server.

You can also use QGIS Server with **NGINX**. Unlike Apache, NGINX does not automatically spawn FastCGI processes. The FastCGI processes are to be started by something else.

Install NGINX:

```
apt install nginx
```

- As a first option, you can use **spawn-fcgi** or **fcgiwrap** to start and manage the QGIS Server processes. Official Debian packages exist for both. When you have no X server running and you need, for example, printing, you can use *xvfb*.
- Another option is to rely on **Systemd**, the init system for GNU/Linux that most Linux distributions use today. One of the advantages of this method is that it requires no other components or processes. It 's meant to be simple, yet robust and efficient for production deployments.

### NGINX Configuration

The **include fastcgi\_params;** used in the previous configuration is important, as it adds the parameters from `/etc/nginx/fastcgi_params`:

```
fastcgi_param QUERY_STRING      $query_string;
fastcgi_param REQUEST_METHOD    $request_method;
fastcgi_param CONTENT_TYPE      $content_type;
fastcgi_param CONTENT_LENGTH    $content_length;

fastcgi_param SCRIPT_NAME       $fastcgi_script_name;
```

(次のページに続く)

```

fastcgi_param  REQUEST_URI          $request_uri;
fastcgi_param  DOCUMENT_URI       $document_uri;
fastcgi_param  DOCUMENT_ROOT      $document_root;
fastcgi_param  SERVER_PROTOCOL    $server_protocol;
fastcgi_param  REQUEST_SCHEME     $scheme;
fastcgi_param  HTTPS              $https if_not_empty;

fastcgi_param  GATEWAY_INTERFACE  CGI/1.1;
fastcgi_param  SERVER_SOFTWARE    nginx/$nginx_version;

fastcgi_param  REMOTE_ADDR        $remote_addr;
fastcgi_param  REMOTE_PORT        $remote_port;
fastcgi_param  SERVER_ADDR        $server_addr;
fastcgi_param  SERVER_PORT        $server_port;
fastcgi_param  SERVER_NAME        $server_name;

# PHP only, required if PHP was built with --enable-force-cgi-redirect
fastcgi_param  REDIRECT_STATUS    200;

```

Moreover, you can use some 環境変数 to configure QGIS Server. In the NGINX configuration file, /etc/nginx/nginx.conf, you have to use fastcgi\_param instruction to define these variables as shown below:

```

location /qgisserver {
    gzip            off;
    include         fastcgi_params;
    fastcgi_param  QGIS_SERVER_LOG_STDERR  1;
    fastcgi_param  QGIS_SERVER_LOG_LEVEL  0;
    fastcgi_pass   unix:/var/run/qgisserver.socket;
}

```

### FastCGI wrappers

**警告:** fcgiwrap is easier to set up than spawn-fcgi, because it's already wrapped in a Systemd service. But it also leads to a solution that is much slower than using spawn-fcgi. With fcgiwrap, a new QGIS Server process is created on each request, meaning that the QGIS Server initialization process, which includes reading and parsing the QGIS project file, is done on each request. With spawn-fcgi, the QGIS Server process remains alive between requests, resulting in much better performance. For that reason, spawn-fcgi is recommended for production use.

### spawn-fcgi

If you want to use spawn-fcgi:

1. The first step is to install the package:

```
apt install spawn-fcgi
```

2. Then, introduce the following block in your NGINX server configuration:

```
location /qgisserver {
    gzip            off;
    include         fastcgi_params;
    fastcgi_pass    unix:/var/run/qgisserver.socket;
}
```

3. And restart NGINX to take into account the new configuration:

```
systemctl restart nginx
```

4. Finally, considering that there is no default service file for spawn-fcgi, you have to manually start QGIS Server in your terminal:

```
spawn-fcgi -s /var/run/qgisserver.socket \
           -U www-data -G www-data -n \
           /usr/lib/cgi-bin/qgis_mapserv.fcgi
```

QGIS Server is now available at <http://qgis.demo/qgisserver>.

---

注釈: When using spawn-fcgi, you may directly define environment variables before running the server. For example: `export QGIS_SERVER_LOG_STDERR=1`

---

Of course, you can add an init script to start QGIS Server at boot time or whenever you want. For example with **systemd**:

1. Edit the file `/etc/systemd/system/qgis-server.service` with this content:

```
[Unit]
Description=QGIS server
After=network.target

[Service]
;; set env var as needed
;Environment="LANG=en_EN.UTF-8"
;Environment="QGIS_SERVER_PARALLEL_RENDERING=1"
;Environment="QGIS_SERVER_MAX_THREADS=12"
;Environment="QGIS_SERVER_LOG_LEVEL=0"
;Environment="QGIS_SERVER_LOG_STDERR=1"
;; or use a file:
;EnvironmentFile=/etc/qgis-server/env
```

(次のページに続く)

(前のページからの続き)

```
ExecStart=spawn-fcgi -s /var/run/qgisserver.socket -U www-data -G www-data -n /  
↳usr/lib/cgi-bin/qgis_mapserv.fcgi
```

**[Install]**

```
WantedBy=multi-user.target
```

2. Then enable and start the service:

```
systemctl enable --now qgis-server
```

**警告:** With the above commands spawn-fcgi spawns only one QGIS Server process.

### fcgiwrap

Using `fcgiwrap` is much easier to setup than `spawn-fcgi` but it's much slower.

1. You first have to install the corresponding package:

```
apt install fcgiwrap
```

2. Then, introduce the following block in your NGINX server configuration:

```
1 location /qgisserver {  
2     gzip            off;  
3     include         fastcgi_params;  
4     fastcgi_pass    unix:/var/run/fcgiwrap.socket;  
5     fastcgi_param   SCRIPT_FILENAME /usr/lib/cgi-bin/qgis_mapserv.fcgi;  
6 }
```

3. Finally, restart NGINX and `fcgiwrap` to take into account the new configuration:

```
systemctl restart nginx  
systemctl restart fcgiwrap
```

QGIS Server is now available at <http://qgis.demo/qgisserver>.

## Systemd

QGIS Server needs a running X Server to be fully usable, in particular for printing. In the case you already have a running X Server, you can use systemd services.

This method, to deploy QGIS Server, relies on two Systemd units to configure: a [Socket unit](#) and a [Service unit](#).

1. The **QGIS Server Socket unit** defines and creates a file system socket, used by NGINX to start and communicate with QGIS Server. The Socket unit has to be configured with `Accept=false`, meaning that the calls to the `accept()` system call are delegated to the process created by the Service unit. It is located in `/etc/systemd/system/qgis-server@.socket`, which is actually a template:

```
[Unit]
Description=QGIS Server Listen Socket (instance %i)

[Socket]
Accept=false
ListenStream=/var/run/qgis-server-%i.sock
SocketUser=www-data
SocketGroup=www-data
SocketMode=0600

[Install]
WantedBy=sockets.target
```

2. Now enable and start sockets:

```
for i in 1 2 3 4; do systemctl enable --now qgis-server@$i.socket; done
```

3. The **QGIS Server Service unit** defines and starts the QGIS Server process. The important part is that the Service process' standard input is connected to the socket defined by the Socket unit. This has to be configured using `StandardInput=socket` in the Service unit configuration located in `/etc/systemd/system/qgis-server@.service`:

```
[Unit]
Description=QGIS Server Service (instance %i)

[Service]
User=www-data
Group=www-data
StandardOutput=null
StandardError=journal
StandardInput=socket
ExecStart=/usr/lib/cgi-bin/qgis_mapserv.fcgi
EnvironmentFile=/etc/qgis-server/env

[Install]
WantedBy=multi-user.target
```

注釈: The QGIS Server *environment variables* are defined in a separate file, `/etc/qgis-server/env`. It could look like this:

```
QGIS_PROJECT_FILE=/etc/qgis/myproject.qgs
QGIS_SERVER_LOG_STDERR=1
QGIS_SERVER_LOG_LEVEL=3
```

4. Now start socket service:

```
for i in 1 2 3 4; do systemctl enable --now qgis-server@$i.service; done
```

5. Finally, for the NGINX HTTP server, let's introduce the configuration for this setup:

```
upstream qgis-server_backend {
    server unix:/var/run/qgis-server-1.sock;
    server unix:/var/run/qgis-server-2.sock;
    server unix:/var/run/qgis-server-3.sock;
    server unix:/var/run/qgis-server-4.sock;
}

server {
    ...

    location /qgis-server {
        gzip off;
        include fastcgi_params;
        fastcgi_pass qgis-server_backend;
    }
}
```

6. Now restart NGINX for the new configuration to be taken into account:

```
systemctl restart nginx
```

Thanks to Oslandia for sharing [their tutorial](#).

### 2.1.3 Xvfb

QGIS Server needs a running X Server to be fully usable, in particular for printing. On servers it is usually recommended not to install it, so you may use `xvfb` to have a virtual X environment.

If you're running the Server in `graphic/X11` environment then there is no need to install `xvfb`. More info at <https://www.itopen.it/qgis-server-setup-notes/>.

1. To install the package:

```
apt install xvfb
```

2. Create the service file, `/etc/systemd/system/xvfb.service`, with this content:

```
[Unit]
Description=X Virtual Frame Buffer Service
After=network.target

[Service]
ExecStart=/usr/bin/Xvfb :99 -screen 0 1024x768x24 -ac +extension GLX +render -
↳noreset

[Install]
WantedBy=multi-user.target
```

3. `xvfb.service` の状態を有効にし、開始し、チェックします :

```
systemctl enable --now xvfb.service
systemctl status xvfb.service
```

4. Then, according to your HTTP server, you should configure the **DISPLAY** parameter or directly use **xvfb-run**.

- Using Apache:

1. Add to your *Fcgid* configuration (see *Apache HTTP Server*):

```
FcgidInitialEnv DISPLAY      ":99"
```

2. Restart Apache for the new configuration to be taken into account:

```
systemctl restart apache2
```

- Using NGINX

- With `spawn-fcgi` using `xvfb-run`:

```
xvfb-run /usr/bin/spawn-fcgi -f /usr/lib/cgi-bin/qgis_mapserv.fcgi \
-s /tmp/qgisserver.socket \
-G www-data -U www-data -n
```

- With the **DISPLAY** environment variable in the HTTP server configuration.


```
fastcgi_param DISPLAY      ":99";
```

## 2.2 Installation on Windows

QGIS Server can also be installed on Windows systems using the 64 bit version of the OSGeo4W network installer (<https://qgis.org/en/site/forusers/download.html>).

A simple procedure is the following:

1. Download and run the OSGeo4W installer
2. Follow the "Advanced Install" and install the **QGIS Desktop**, **QGIS Server apache** and **mod\_fcgid** packages.



3. Apache is not directly installed as a service on Windows. You need to:
  1. Right-click the OSGeo4W.bat file at the root of the C:\OSGeo4W64\ folder (if the default installation paths have been used) and select *Run as administrator*
  2. In the console, run `apache-install.bat`, which will output

```
> apache-install.bat
Installing the 'Apache OSGeo4W Web Server' service
The 'Apache OSGeo4W Web Server' service is successfully installed.
Testing httpd.conf....
Errors reported here must be corrected before the service can be started.
...
```

The service is started as you can notice in the report. But the server may fail to run due to missing custom configuration.

4. Edit the C:\OSGeo4w64\apps\apache\conf\httpd.conf file with the following changes (various other combinations are possible):

Purpose	Existing config	Replacement
(Optional) Customize the address to listen to using an IP and/or port, You can and add as many entries as you wish.	<code>Listen \${SRVPORT}</code>	<code>Listen localhost:8080</code>
Indicate where to find the script files	<code>ScriptAlias /cgi-bin/ "\$ ↪{SRVROOT}/cgi-bin/"</code>	<code>ScriptAlias /cgi-bin/ ↪"C:/OSGeo4W64/apps/ ↪qgis/bin/"</code>
Provide permissions on the script folder	<code>&lt;Directory "\${SRVROOT}/ ↪cgi-bin"&gt;     AllowOverride None     Options None     Require all granted &lt;/Directory&gt;</code>	<code>&lt;Directory "C:/ ↪OSGeo4W64/apps/qgis/ ↪bin"&gt;     SetHandler cgi- ↪script     AllowOverride None     Options ExecCGI     Require all granted &lt;/Directory&gt;</code>
Enable file extensions to use for script files. Uncomment and complete	<code>#AddHandler cgi-script . ↪cgi</code>	<code>AddHandler cgi-script . ↪cgi .exe</code>
Add more OSGeo4W custom configuration variables	<code># parse OSGeo4W apache_ ↪conf files IncludeOptional "C:/ ↪OSGeo4W64/httpd.d/ ↪httpd_*.conf"</code>	<code># parse OSGeo4W apache_ ↪conf files IncludeOptional "C:/ ↪OSGeo4W64/httpd.d/ ↪httpd_*.conf" SetEnv GDAL_DATA "C:/ ↪OSGeo4W64/share/gdal" SetEnv QGIS_AUTH_DB_DIR_ ↪PATH "C:/OSGeo4W64/ ↪apps/qgis/resources"</code>

- Restart the Apache web server

```
> apache-restart.bat
```

- Open browser window to testing a GetCapabilities request to QGIS Server. Replace localhost:8080 with the IP and port you set to listen.

```
http://localhost:8080/cgi-bin/qgis_mapserv.fcgi.exe?SERVICE=WMS&VERSION=1.3.0&  
↪REQUEST=GetCapabilities
```

A XML file with the capabilities should be returned. Your server is ready to use.

### 2.3 Serve a project

Now that QGIS Server is installed and running, we just have to use it.

Obviously, we need a QGIS project to work on. Of course, you can fully customize your project by defining contact information, precise some restrictions on CRS or even exclude some layers. Everything you need to know about that is described later in *Configure your project*.

But for now, we are going to use a simple project already configured and previously downloaded in `/home/qgis/projects/world.qgs`, as described above.


By opening the project and taking a quick look on layers, we know that 4 layers are currently available:

- airports
- places
- countries
- countries\_shapeburst

You don't have to understand the full request for now but you may retrieve a map with some of the previous layers thanks to QGIS Server by doing something like this in your web browser to retrieve the *countries* layer:

```
http://qgis.demo/qgisserver?  
MAP=/home/qgis/projects/world.qgs&  
LAYERS=countries&  
SERVICE=WMS&  
VERSION=1.3.0&  
REQUEST=GetMap&  
CRS=EPSG:4326&  
WIDTH=400&  
HEIGHT=200&  
BBOX=-90,-180,90,180
```

If you obtain the next image, then QGIS Server is running correctly:



☒ 2.1: Server response to a basic GetMap request

Note that you may define **QGIS\_PROJECT\_FILE** environment variable to use a project by default instead of giving a **MAP** parameter (see 環境変数).

For example with spawn-fcgi:

```
export QGIS_PROJECT_FILE=/home/qgis/projects/world.qgs
spawn-fcgi -f /usr/lib/bin/cgi-bin/qgis_mapserv.fcgi \
  -s /var/run/qgisserver.socket \
  -U www-data -G www-data -n
```

## 2.4 Configure your project

To provide a new QGIS Server WMS, WFS or WCS, you have to create a QGIS project file with some data or use one of your current project. Define the colors and styles of the layers in QGIS and the project CRS, if not already defined.




図 2.2: QGIS サーバーの WMS / WFS / WCS プロジェクトの定義

Then, go to the *QGIS Server* menu of the *Project Properties...* dialog and provide some information about the OWS in the fields under *Service Capabilities*. This will appear in the *GetCapabilities* response of the WMS, WFS or WCS. If you don't check  *Service capabilities*, QGIS Server will use the information given in the `wms_metadata.xml` file located in the `cgi-bin` folder.

## 2.4.1 WMS 機能

guiabel:WMS capabilities セクションでは、*Advertised* 範囲 の下のフィールドに最小値と最大値の X と Y を入力することで、WMS GetCapabilities レスポンスでアドバタイズされた範囲を定義できます。guiabel:現在のキャンパス範囲を使用 をクリックすると、これらの値は QGIS 地図キャンパスに現在表示されている範囲に設定されます。  *CRS 制限* をチェックすると、QGIS サーバが地図をレンダリングする際に提供する座標参照系 (CRS) を制限できます。提供される CRS を制限すると WMS GetCapabilities レスポンスのサイズが小さくなるため、制限することをお勧めします。以下の  ボタンを使用して、座標参照系セレクトからこれらの CRS を選択するか、使用中 をクリックして QGIS プロジェクトで使用されている CRS をリストに追加します。

If you have print layouts defined in your project, they will be listed in the `GetProjectSettings` response, and they can be used by the `GetPrint` request to create prints, using one of the print layouts as a template. This is a QGIS-specific extension to the WMS 1.3.0 specification. If you want to exclude any print layout from being published by the WMS, check  *Exclude layouts* and click the  button below. Then, select a print layout from the *Select print layout* dialog in order to add it to the excluded layouts list.

If you want to exclude any layer or layer group from being published by the WMS, check  *Exclude Layers* and click the  button below. This opens the *Select restricted layers and groups* dialog, which allows you to choose the layers and groups that you don't want to be published. Use the `Shift` or `Ctrl` key if you want to select multiple entries. It is recommended that you exclude from publishing the layers that you don't need as this reduces the size of the WMS GetCapabilities response which leads to faster loading times on the client side.

If you check  *Use layer ids as name*, layer ids will be used to reference layers in the `GetCapabilities` response or `GetMap` `LAYERS` parameter. If not, layer name or short name if defined (see `vectorservermenu`) is used.

You can receive requested `GetFeatureInfo` as plain text, XML and GML. The default is XML.

If you wish, you can check  *Add geometry to feature response*. This will include the bounding box for each feature in the `GetFeatureInfo` response. See also the `WITH_GEOMETRY` parameter.

As many web clients can't display circular arcs in geometries you have the option to segmentize the geometry before sending it to the client in a `GetFeatureInfo` response. This allows such clients to still display a feature's geometry (e.g. for highlighting the feature). You need to check the  *Segmentize feature info geometry* to activate the option.

You can also use the *GetFeatureInfo geometry precision* option to set the precision of the `GetFeatureInfo` geometry. This enables you to save bandwidth when you don't need the full precision.

If you want QGIS Server to advertise specific request URLs in the WMS GetCapabilities response, enter the corresponding URL in the *Advertised URL* field.

Furthermore, you can restrict the maximum size of the maps returned by the `GetMap` request by entering the maximum width and height into the respective fields under *Maximums for GetMap request*.

You can change the *Quality for JPEG images* factor. The quality factor must be in the range 0 to 100. Specify 0 for maximum compression, 100 for no compression.

You can change the limit for atlas features to be printed in one request by setting the *Maximum features for Atlas print requests* field.

When QGIS Server is used in tiled mode (see *TILED parameter*), you can set the *Tile buffer in pixels*. The recommended value is the size of the largest symbol or line width in your QGIS project.

レイヤーの一つが地図ヒントディスプレイを使用している場合（つまり式を使ってテキストを表示するために）これは GetFeatureInfo 出力内で表示されます。レイヤーは、その属性のいずれかの値マップを使用している場合は、この情報には、GetFeatureInfo 出力に表示されません。

### 2.4.2 WFS 機能

で WFS 機能 エリア WFS として公開し、それらが更新を許可するかどうかを指定、操作を挿入し、削除したいレイヤーを選択できます。:guilabel:`WFS 機能` セクションの 宣伝 URL フィールドに URL を入力すると、QGI サーバーは、WFS の GetCapabilities 応答中でこの特定の URL を宣伝します。

### 2.4.3 WCS 機能

WCS 機能 エリア、WCS として公開したいレイヤーを選択できます。WCS 機能 セクションで 宣伝 URL フィールドに URL を入力すると、QGIS サーバーは WCS の GetCapabilities 応答でこの特定の URL を宣伝します。

### 2.4.4 OWS を微調整する

For vector layers, the *Fields* menu of the *Layer Layer Properties* dialog allows you to define for each attribute if it will be published or not. By default, all the attributes are published by your WMS and WFS. If you don't want a specific attribute to be published, uncheck the corresponding checkbox in the *WMS* or *WFS* column.

You can overlay watermarks over the maps produced by your WMS by adding text annotations or SVG annotations to the project file. See the *sec\_annotations* section for instructions on creating annotations. For annotations to be displayed as watermarks on the WMS output, the *Fixed map position* checkbox in the *Annotation text* dialog must be unchecked. This can be accessed by double clicking the annotation while one of the annotation tools is active. For SVG annotations, you will need either to set the project to save absolute paths (in the *General* menu of the *Project Properties...* dialog) or to manually modify the path to the SVG image so that it represents a valid relative path.

## 2.5 Integration with third parties

QGIS Server provides standard OGC web services like *WMS*, *WFS*, etc. thus it can be used by a wide variety of end user tools.

### 2.5.1 Integration with QGIS Desktop

QGIS Desktop is the map designer where QGIS Server is the map server. The maps or QGIS projects will be served by the QGIS Server to provide OGC standards. These QGIS projects can either be files or entries in a database (by using *Project Save to PostgreSQL* in QGIS Desktop).

Furthermore, dedicated update workflow must be established to refresh a project used by a QGIS Server (ie. copy project files into server location and restart QGIS Server). For now, automated processes (as server reloading over message queue service) are not implemented yet.

### 2.5.2 Integration with MapProxy

MapProxy is a tile cache server and as it can read and serve any WMS/WMTS map server, it can be directly connected to QGIS server web services and improve end user experience.

### 2.5.3 Integration with QWC2

QWC2 is a responsive web application dedicated to QGIS Server. It helps you to build a highly customized map viewer with layer selection, feature info, etc.. Also many plugins are available like authentication or print service, the full list is available in this [repository](#).



## 第3章 サービス

QGIS サーバーでは、Open Geospatial Consortium (OGC) に記載されているように、標準プロトコルに従ってデータを提供できます。

- WMS 1.1.1 and 1.3.0
- WFS 1.0.0 and 1.1.0
- OGC API - Features (WFS3)
- WCS 1.0.0 and 1.1.1
- WMTS 1.0.0

QGIS レンダリングエンジンのおかげでその振る舞いをカスタマイズする可能性を大いに高めるオリジナルの規格に加えて、追加のベンダーパラメータと要求がサポートされています。

### 3.1 Basics

This section describes concepts and parameters mutually shared by services. Some of these are standard and defined in OGC specifications while others are very specific to QGIS Server.

Standard concepts:

Concept	説明
<i>SERVICE</i>	Name of the service
<i>REQUEST</i>	Name of the request

Vendor concepts:

Concept	説明
<i>MAP</i>	QGIS project file
<i>FILE_NAME</i>	File name of the downloaded file
<i>Short name</i>	Short name definition

### 3.1.1 SERVICE

This standard parameter allows to specify the name of the service to use for a specific *request* and has to be formed like SERVICE=NAME.

URL example for the WMS service:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&...
```

---

注釈: Not available for REST based services like *WFS3 (OGC API Features)*.

---

### 3.1.2 REQUEST

This standard parameter allows to specify the name of the request to execute for a specific *service* and has to be formed like REQUEST=RequestName.

URL example for the **GetCapabilities** request:

```
http://localhost/qgisserver?  
REQUEST=GetCapabilities  
&...
```

---

注釈: Not available for REST based services like *WFS3 (OGC API Features)*.

---

### 3.1.3 MAP

This vendor parameter allows to define the QGIS project file to use. It may be an absolute path or a path relative to the location of the server executable `qgis_mapserv.fcgi`. MAP is mandatory by default because a request needs a QGIS project to actually work. However, the **QGIS\_PROJECT\_FILE** environment variable may be used to define a default QGIS project. In this specific case, MAP is no longer a required parameter. For further information you may refer to the [高度な構成](#) chapter.

URL example:

```
http://localhost/qgisserver?  
MAP=/tmp/QGIS-Training-Data/exercise_data/qgis-server-tutorial-data/world.qgs  
&...
```

### 3.1.4 FILE\_NAME

If this vendor parameter is set, the server response will be sent to the client as a file attachment with the specified file name.

URL example to save an XML **GetCapabilities** document:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetCapabilities
&FILE_NAME=wms_capabilities.xml
&...
```

注釈: Not available for REST based services like *WFS3 (OGC API Features)*.

### 3.1.5 Short name

A number of elements have both a **short name** and a **title**. The short name is a text string used for machine-to-machine communication while the title is for the benefit of humans. For example, a dataset might have the descriptive title “ *Maximum Atmospheric Temperature* ” and be requested using the abbreviated short name “ *AT-MAX* ”. You can set title, short name and abstract for:

- **Layers:** right-click on a layer and choose *Properties... QGIS Server Description*.
- **Groups:** right-click on a group and select *Set Group WMS data*
- **Project:** go to *Project Properties... QGIS Server Service Capabilities*.




図 3.1: Set group WMS data dialog

Thus, the short name may be used to identify these items when interacting with QGIS Server. For example with the standard **LAYERS** parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
```

(次のページに続く)

```
&LAYERS=shortname1,shortname2
&...
```

## 3.2 Web 地図サービス (WMS)

The **1.1.1** and **1.3.0** WMS standards implemented in QGIS Server provide a HTTP interface to request map or legend images generated from a QGIS project. A typical WMS request defines the QGIS project to use, the layers to render as well as the image format to generate. Basic support is also available for **Styled Layer Descriptor (SLD)**.

Specifications:

- WMS 1.1.1
- WMS 1.3.0
- SLD 1.1.0 WMS profile

Standard requests provided by QGIS Server:

Request	説明
<i>GetCapabilities</i>	Returns XML metadata with information about the server
<i>GetMap</i>	Returns a map
<i>GetFeatureInfo</i>	Retrieves data (geometry and values) for a pixel location
<i>GetLegendGraphics</i>	Returns legend symbols
<i>GetStyle(s)</i>	Returns XML document with style description in SLD
<i>DescribeLayer</i>	Returns information about WFS and WCS availability respectively for vector and raster layers

Vendor requests provided by QGIS Server:

Request	説明
<i>GetPrint</i>	Returns a QGIS layout
<i>GetProjectSettings</i>	Returns specific information about QGIS Server
<i>GetSchemaExtension</i>	Returns XML metadata about optional extended capabilities

### 3.2.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetCapabilities</b> )
<i>VERSION</i>	いいえ	Version of the service

The **GetCapabilities** request supports as well the following vendor parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/qgis_server?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetCapabilities
```

### 3.2.2 GetMap

Standard parameters for the **GetMap** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetMap</b> )
<i>VERSION</i>	はい	Version of the service
<i>LAYERS</i>	いいえ	Layers to display
<i>STYLES</i>	いいえ	Layers' style
<i>SRS / CRS</i>	はい	座標参照系
<i>BBOX</i>	はい	Map extent
<i>WIDTH</i>	はい	Width of the image in pixels
<i>HEIGHT</i>	はい	Height of the image in pixels
<i>FORMAT</i>	いいえ	Image format
<i>TRANSPARENT</i>	いいえ	透明な背景
<i>SLD</i>	いいえ	URL of an SLD to be used for styling
<i>SLD_BODY</i>	いいえ	In-line SLD (XML) to be used for styling

In addition to the standard ones, QGIS Server supports *redlining*, *external WMS layers* as well as the following extra parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>BGCOLOR</i>	いいえ	Specify the background color
<i>DPI</i>	いいえ	Specify the output resolution
<i>IMAGE_QUALITY</i>	いいえ	JPEG compression
<i>OPACITIES</i>	いいえ	Opacity for layer or group
<i>FILTER</i>	いいえ	Subset of features
<i>SELECTION</i>	いいえ	Highlight features
<i>FILE_NAME</i>	いいえ	File name of the downloaded file Only for <i>FORMAT=application/dxf</i>
<i>FOR-MAT_OPTIONS</i>	いいえ	Options of the specified file format Only for <i>FORMAT=application/dxf</i>
<i>TILED</i>	いいえ	Working in <i>tiled mode</i>

URL example:

```

http://localhost/qgis_server?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetMap
&MAP=/home/qgis/projects/world.qgs
&LAYERS=mylayer1,mylayer2,mylayer3
&STYLES=style1,default,style3
&OPACITIES=125,200,125
&CRS=EPSG:4326
&WIDTH=400
&HEIGHT=400
&FORMAT=image/png
&TRANSPARENT=TRUE
&DPI=300
&TILED=TRUE
    
```

## VERSION

This parameter allows to specify the version of the service to use. Available values for the *VERSION* parameter are:

- 1.1.1
- 1.3.0

According to the version number, slight differences have to be expected as explained later for the next parameters:

- CRS / SRS
- BBOX

## LAYERS

This parameter allows to specify the layers to display on the map. Names have to be separated by a comma.

In addition, QGIS Server introduced some options to select layers by:

- a *short name*
- the layer id

The project option allowing to select layers by their id is in *QGIS Server WMS Capabilities* menu of the *Project Properties...* dialog. Check the *Use layer ids as names* checkbox to activate this option.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&LAYERS=mylayerid1,mylayerid2
&...
```

## STYLES

This parameter can be used to specify a layer's style for the rendering step. Styles have to be separated by a comma. The name of the default style is `default`.

## SRS / CRS

This parameter allows to indicate the map output Spatial Reference System in WMS **1.1.1** and has to be formed like `EPSG:XXXX`. Note that CRS is also supported if current version is **1.1.1**.

For WMS **1.3.0**, CRS parameter is preferable but SRS is also supported.

Note that if both CRS and SRS parameters are indicated in the request, then it's the current version indicated in `VERSION` parameter which is decisive.

In the next case, the SRS parameter is kept whatever the `VERSION` parameter because CRS is not indicated:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&SRS=EPSG:2854
&...
```

In the next case, the SRS parameter is kept instead of CRS because of the `VERSION` parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
```

(次のページに続く)

(前のページからの続き)

```
&VERSION=1.1.1
&CRS=EPSG:4326
&SRS=EPSG:2854
&...
```

In the next case, the CRS parameter is kept instead of SRS because of the VERSION parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&CRS=EPSG:4326
&SRS=EPSG:2854
&...
```

### BBOX

This parameter allows to specify the map extent with units according to the current CRS. Coordinates have to be separated by a comma.

The BBOX parameter is formed like `min_a,min_b,max_a,max_b` but a and b axis definition is different according to the current VERSION parameter:

- in WMS **1.1.1**, the axis ordering is always east/north
- in WMS **1.3.0**, the axis ordering depends on the CRS authority

For example in case of EPSG:4326 and WMS **1.1.1**, a is the longitude (east) and b the latitude (north), leading to a request like:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.1.1
&SRS=epsg:4326
&BBOX=-180,-90,180,90
&...
```

But in case of WMS **1.3.0**, the axis ordering defined in the EPSG database is north/east so a is the latitude and b the longitude:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&CRS=epsg:4326
```

(次のページに続く)

(前のページからの続き)

```
&BBOX=-90,-180,90,180  
&...
```

## WIDTH

This parameter allows to specify the width in pixels of the output image.

## HEIGHT

This parameter allows to specify the height in pixels of the output image.

## FORMAT

This parameter may be used to specify the format of map image. Available values are:

- jpg
- jpeg
- image/jpeg
- image/png
- image/png; mode=1bit
- image/png; mode=8bit
- image/png; mode=16bit
- application/dxf: only layers that have read access in the WFS service are exported in the DXF format

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS&VERSION=1.3.0  
&REQUEST=GetMap  
&FORMAT=application/dxf  
&LAYERS=Haltungen,Normschacht,Spezialbauwerke  
&CRS=EPSG%3A21781  
&BBOX=696136.28844801,245797.12108743,696318.91114315,245939.25832905  
&WIDTH=1042  
&HEIGHT=811  
&FORMAT_OPTIONS=MODE:SYMBOLLAYERSYMBOLGY;SCALE:250  
&FILE_NAME=plan.dxf
```

### TRANSPARENT

This boolean parameter can be used to specify the background transparency. Available values are (not case sensitive):

- TRUE
- FALSE

However, this parameter is ignored if the format of the image indicated with `FORMAT` is different from PNG.

### BGCOLOR

This parameter allows to indicate a background color for the map image. However it cannot be combined with `TRANSPARENT` parameter in case of PNG images (transparency takes priority). The colour may be literal or in hexadecimal notation.

URL example with the literal notation:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetMap  
&VERSION=1.3.0  
&BGCOLOR=green  
&...
```

URL example with the hexadecimal notation:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetMap  
&VERSION=1.3.0  
&BGCOLOR=0x00FF00  
&...
```

### DPI

This parameter can be used to specify the requested output resolution.

## IMAGE\_QUALITY

This parameter is only used for JPEG images. By default, the JPEG compression is -1.

You can change the default per QGIS project in the *OWS Server WMS capabilities* menu of the *Project Properties...* dialog. If you want to override it in a GetMap request you can do it using the `IMAGE_QUALITY` parameter.

## OPACITIES

Comma separated list of opacity values. Opacity can be set on layer or group level. Allowed values range from 0 (fully transparent) to 255 (fully opaque).

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&WIDTH=400
&HEIGHT=200
&CRS=EPSG:4326
&LAYERS=countries,places
&BBOX=42,-6,52,15
&OPACITIES=255,0
```



図 3.2: To the left `OPACITIES=255,0` and to the right `OPACITIES=255,255`

## FILTER

A subset of layers can be selected with the `FILTER` parameter. The syntax is basically the same as for the QGIS subset string. However, there are some restrictions to avoid SQL injections into databases via QGIS Server. If a dangerous string is found in the parameter, QGIS Server will return the next error:

```
<ServiceExceptionReport>
  <ServiceException code="Security">The filter string XXXXXXXXXX has been rejected.
  ↳because of security reasons.
  Note: Text strings have to be enclosed in single or double quotes. A space between.
  ↳each word / special character is mandatory. (次のページに続く)
```

```

Allowed Keywords and special characters are IS,NOT,NULL,AND,OR,IN,=,<,<=,>,>=,!=,',
↔','(',') ,DMETAPHONE,SOUNDEX.
Not allowed are semicolons in the filter expression.</ServiceException>
</ServiceExceptionReport>

```

URL example:

```

http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&WIDTH=400
&HEIGHT=300
&CRS=EPSG:4326
&BBOX=41,-6,52,10
&LAYERS=countries_shapeburst,countries,places
&FILTER=countries_shapeburst,countries:"name" = 'France';places: "name" = 'Paris'

```



図 3.3: Server response to a GetMap request with FILTER parameter

In this example, the same filter "name" = 'France' is applied to layers countries and countries\_shapeburst, while the filter "name" = 'Paris' is only applied to places.

---

**注釈:** It is possible to make attribute searches via GetFeatureInfo and omit the X/Y parameter if a FILTER is there. QGIS Server then returns info about the matching features and generates a combined bounding box in the XML output.

---

## SELECTION

The SELECTION parameter can highlight features from one or more layers. Vector features can be selected by passing comma separated lists with feature ids.

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetMap  
&LAYERS=mylayer1,mylayer2  
&SELECTION=mylayer1:3,6,9;mylayer2:1,5,6  
&...
```

The following image presents the response from a GetMap request using the SELECTION option e.g. <http://myserver.com/...&SELECTION=countries:171,65>.

As those features id's correspond in the source dataset to **France** and **Romania** they're highlighted in yellow.



図 3.4: SELECTION パラメーターを指定した GetMap リクエストに対するサーバーの応答

### FORMAT-OPTIONS

This parameter can be used to specify options for the selected format. Only for `FORMAT=application/dxf`. A list of key:value pairs separated by semicolon:

- `SCALE`: to be used for symbology rules, filters and styles (not actual scaling of the data - data remains in the original scale).
- `MODE`: corresponds to the export options offered in the QGIS Desktop DXF export dialog. Possible values are `NOSYMBOLLOGY`, `FEATURESYMBOLLOGY` and `SYMBOLLAYERSYMBOLLOGY`.
- `LAYERSATTRIBUTES`: specify a field that contains values for DXF layer names - if not specified, the original QGIS layer names are used.
- `USE_TITLE_AS_LAYERNAME`: if enabled, the title of the layer will be used as layer name.
- `CODEC`: specify a codec to be used for encoding. Default is `ISO-8859-1` check the QGIS desktop DXF export dialog for valid values.
- `NO_MTEXT`: Use `TEXT` instead of `MTEXT` for labels.
- `FORCE_2D`: Force 2D output. This is required for polyline width.

### TILED

For performance reasons, QGIS Server can be used in tiled mode. In this mode, the client requests several small fixed size tiles, and assembles them to form the whole map. Doing this, symbols at or near the boundary between two tiles may appeared cut, because they are only present in one of the tile.

Set the `TILED` parameter to `TRUE` to tell QGIS Server to work in *tiled* mode, and to apply the *Tile buffer* configured in the QGIS project (see *Configure your project*).

When `TILED` is `TRUE` and when a non-zero *Tile buffer* is configured in the QGIS project, features outside the tile extent are drawn to avoid cut symbols at tile boundaries.

`TILED` defaults to `FALSE`.

### 3.2.3 GetFeatureInfo

Standard parameters for the **GetFeatureInfo** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetFeatureInfo</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>QUERY_LAYERS</i>	はい	Layers to query
<i>LAYERS</i>	はい	Layers to display (identical to <i>QUERY_LAYERS</i> )
<i>STYLES</i>	いいえ	Layers' style
<i>SRS</i> / <i>CRS</i>	はい	座標参照系
<i>BBOX</i>	いいえ	Map extent
<i>WIDTH</i>	はい	Width of the image in pixels
<i>HEIGHT</i>	はい	Height of the image in pixels
<i>TRANSPARENT</i>	いいえ	透明な背景
<i>INFO_FORMAT</i>	いいえ	出力形式
<i>FEATURE_COUNT</i>	いいえ	Maximum number of features to return
<i>I</i>	いいえ	Pixel column of the point to query
<i>X</i>	いいえ	Same as <i>I</i> parameter, but in WMS 1.1.1
<i>J</i>	いいえ	Pixel row of the point to query
<i>Y</i>	いいえ	Same as <i>J</i> parameter, but in WMS 1.1.1
<i>WMS_PRECISION</i>	いいえ	The precision (number of digits) to be used when returning geometry (see <a href="#">how to add geometry to feature response</a> ). The default value is -1 meaning that the precision defined in the project is used.

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>FILTER</i>	いいえ	Subset of features
<i>FI_POINT_TOLERANCE</i>	いいえ	Tolerance in pixels for point layers
<i>FI_LINE_TOLERANCE</i>	いいえ	ラインレイヤでの許容誤差 (ピクセル)
<i>FI_POLYGON_TOLERANCE</i>	いいえ	Tolerance in pixels for polygon layers
<i>FILTER_GEOM</i>	いいえ	Geometry filtering
<i>WITH_MAPTIP</i>	いいえ	Add map tips to the output
<i>WITH_GEOMETRY</i>	いいえ	Add geometry to the output

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&VERSION=1.3.0  
&REQUEST=GetMap  
&MAP=/home/qgis/projects/world.qgs  
&LAYERS=mylayer1,mylayer2,mylayer3  
&CRS=EPSG:4326  
&WIDTH=400  
&HEIGHT=400  
&INFO_FORMAT=text/xml  
&TRANSPARENT=TRUE  
&QUERY_LAYERS=mylayer1  
&FEATURE_COUNT=3  
&I=250  
&J=250
```

### INFO\_FORMAT

このパラメータは結果のフォーマットを指定するために使用されます。利用可能な値は以下のとおりです：

- text/xml
- text/html
- text/plain
- application/vnd.ogc.gml
- application/json

## QUERY\_LAYERS

This parameter specifies the layers to display on the map. Names are separated by a comma.

In addition, QGIS Server introduces options to select layers by:

- short name
- layer id

See the LAYERS parameter defined in *GetMap* for more information.

## FEATURE\_COUNT

このパラメータでは、レイヤごとに返す地物の最大数を指定します。例えば、QUERY\_LAYERS が layer1, layer2 に設定され、FEATURE\_COUNT が 3 に設定されている場合、layer1 から最大 3 つの地物が返されます。同様に、layer2 から最大 3 つの地物が返されます。

By default, only 1 feature per layer is returned.

## I

This parameter, defined in WMS 1.3.0, allows you to specify the pixel column of the query point.

## X

Same parameter as I, but defined in WMS 1.1.1.

## J

This parameter, defined in WMS 1.3.0, allows you to specify the pixel row of the query point.

## Y

Same parameter as J, but defined in WMS 1.1.1.

## FI\_POINT\_TOLERANCE

このパラメータではラインレイヤでの許容誤差（ピクセル）を指定します。

## FI\_LINE\_TOLERANCE

This parameter specifies the tolerance in pixels for line layers.

## FI\_POLYGON\_TOLERANCE :

This parameter specifies the tolerance in pixels for polygon layers.

## FILTER\_GEOM

This parameter specifies a WKT geometry with which features have to intersect.

## WITH\_MAPTIP

This parameter specifies whether to add map tips to the output.

Available values are (not case sensitive):

- TRUE
- FALSE

## WITH\_GEOMETRY

This parameter specifies whether to add geometries to the output. To use this feature you must first enable the *Add geometry to feature response* option in the QGIS project. See *Configure your project*.

Available values are (not case sensitive):

- TRUE
- FALSE

### 3.2.4 GetLegendGraphics

Standard parameters for the **GetLegendGraphics** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetLegendGraphics</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>LAYERS</i>	はい	Layers to display
<i>STYLES</i>	いいえ	Layers' style
<i>SRS / CRS</i>	いいえ	座標参照系
<i>BBOX</i>	いいえ	Map extent
<i>WIDTH</i>	いいえ	Width of the image in pixels
<i>HEIGHT</i>	いいえ	Height of the image in pixels
<i>FORMAT</i>	いいえ	Legend format
<i>TRANSPARENT</i>	いいえ	透明な背景

In addition to the standard ones, QGIS Server supports extra parameters to change the size of the legend elements or the font properties for layer titles and item labels:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>SRCWIDTH</i>	いいえ	Map width
<i>SRCHEIGHT</i>	いいえ	Map height
<i>SHOWFEATURECOUNT</i>	いいえ	Add feature count of features
<i>RULE</i>	いいえ	Rule symbol to render
<i>RULELABEL</i>	いいえ	Item labels rendering
<i>BOXSPACE</i>	いいえ	Space between legend frame and content (mm)
<i>LAYERSPACE</i>	いいえ	Vertical space between layers (mm)
<i>LAYERTITLESPACE</i>	いいえ	Vertical space between layer title and items (mm)
<i>SYMBOLSPACE</i>	いいえ	Vertical space between symbol and items (mm)
<i>ICONLABELSPACE</i>	いいえ	Horizontal space between symbol and label (mm)
<i>SYMBOLWIDTH</i>	いいえ	Width of the symbol preview (mm)
<i>SYMBOLHEIGHT</i>	いいえ	Height of the symbol preview (mm)
<i>LAYERTITLE</i>	いいえ	Layer title rendering
<i>LAYERFONTFAMILY</i>	いいえ	Layer font family
<i>LAYERFONTBOLD</i>	いいえ	Layer title bold rendering
<i>LAYERFONTSIZE</i>	いいえ	Layer title font size (pt)
<i>LAYERFONTITALIC</i>	いいえ	Layer title italic rendering
<i>LAYERFONTCOLOR</i>	いいえ	Layer title color
<i>ITEMFONTFAMILY</i>	いいえ	Item font family
<i>ITEMFONTBOLD</i>	いいえ	Item label bold rendering
<i>ITEMFONTSIZE</i>	いいえ	Item label font size (pt)
<i>ITEMFONTITALIC</i>	いいえ	Item label italic rendering
<i>ITEMFONTCOLOR</i>	いいえ	Item label color

## BBOX

This parameter can be used to specify the geographical area for which the legend should be built (its format is described [here](#)) but cannot be combined with the *RULE* parameter. The *SRS/CRS* parameter becomes mandatory when using the *BBOX* parameter.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,airports
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
```

注釈: When the *BBOX* parameter is defined, the legend is referred to as a *content based legend*.

## WIDTH

This parameter is not used by default but becomes mandatory when the RULE parameter is set. In this case it allows to specify the width in pixels of the output image.

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYER=testlayer%20%C3%A8%C3%A9  
&RULE=rule1  
&WIDTH=30  
&HEIGHT=30
```

## HEIGHT

This parameter is not used by default but becomes mandatory when the RULE parameter is set. In this case it allows to specify the height in pixels of the output image.

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYER=testlayer%20%C3%A8%C3%A9  
&RULE=rule1  
&WIDTH=30  
&HEIGHT=30
```

## FORMAT

This parameter may be used to specify the format of legend image. Available values are:

- image/jpeg
- image/png
- application/json

For JSON, symbols are encoded with Base64 and most other options related to layout or fonts are not taken into account because the legend must be built on the client side. The RULE parameter cannot be combined with this format.

URL example with the corresponding JSON output:

```
http://localhost/qgisserver?  
SERVICE=WMS&  
REQUEST=GetLegendGraphics&  
LAYERS=airports&  
FORMAT=application/json
```

And the corresponding JSON output:

```
{
  "nodes": [
    {
      "icon": "<base64 icon>",
      "title": "airports",
      "type": "layer"
    }
  ],
  "title": ""
}
```

### SRCWIDTH

This parameter may be defined when the RULE parameter is set. In this case, the SRCWIDTH value is forwarded to the underlying GetMap request as the WIDTH parameter while the WIDTH parameter of GetLegendGraphics is used for the image legend size.

### SRCHEIGHT


This parameter may be defined when the RULE parameter is set. In this case, the SRCHEIGHT value is forwarded to the underlying GetMap request as the HEIGHT parameter while the HEIGHT parameter of GetLegendGraphics is used for the image legend size.

### SHOWFEATURECOUNT

This parameter can be used to activate feature count in the legend. Available values are (not case sensitive):

- TRUE
- FALSE

For example:



## RULE

This parameter is available on layers with *Rule-based* rendering and allows to build a legend with only the named rule symbol. It cannot be combined with BBOX parameter nor the JSON format.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=mylayer,  
&RULE=myrulename
```

## RULELABEL

This parameter allows to control the item label rendering. Available values are (not case sensitive):

- TRUE: display item label
- FALSE: hide item label
- AUTO: hide item label for layers with *Single symbol* rendering

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=countries,airports  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&RULELABEL=AUTO
```



図 3.5: Legend rendering without label for single symbol layers

### BOXSPACE

This parameter allows to specify the space between legend frame and content in millimeters. By default, the space value is 2 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&BOXSPACE=0
```




図 3.6: To the left BOXSPACE=0 and to the right BOXSPACE=15

## LAYERSPACE

This parameter allows to specify the vertical space between layers in millimeters. By default, the space value is 3 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&LAYERSPACE=0
```



☒ 3.7: To the left LAYERSPACE=0 and to the right LAYERSPACE=10

## LAYERTITLESPACE

This parameter allows to specify the vertical space between layer title and items following in millimeters. By default the space value is 3 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&LAYERTITLESPACE=0
```




図 3.8: To the left LAYERTITLESAPCE=0 and to the right LAYERTITLESAPCE=10

### SYMBOLSPACE

This parameter allows to specify the vertical space between symbol and item following in millimeters. By default the space value is 2 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLSPACE=0
```




図 3.9: To the left SYMBOLSPACE=0 and to the right SYMBOLSPACE=5

## ICONLABELSPACE

This parameter allows to specify the horizontal space between symbol and label text in millimeters. By default the space value is 2 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&ICONLABELSPACE=0
```



図 3.10: To the left `ICONLABELSPACE=0` and to the right `ICONLABELSPACE=10`

## SYMBOLWIDTH

This parameter allows to specify the width of the symbol preview in millimeters. By default the width value is 7 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLWIDTH=2
```



図 3.11: To the left SYMBOLWIDTH=2 and to the right SYMBOLWIDTH=20

### SYMBOLHEIGHT

This parameter allows to specify the height of the symbol preview in millimeters. By default the height value is 4 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLHEIGHT=2
```



図 3.12: To the left SYMBOLHEIGHT=2 and to the right SYMBOLHEIGHT=6

## LAYERTITLE

This parameter specifies whether to render layer title.

Available values are (not case sensitive):

- TRUE (default value)
- FALSE

## LAYERFONTFAMILY

This parameter specifies the font family to use for rendering layer title.

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=countries  
&LAYERFONTFAMILY=monospace
```

## LAYERFONTBOLD

This parameter specifies whether the layer title is rendered in bold. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&LAYERFONTBOLD=TRUE
```



☒ 3.13: Legend with LAYERFONTBOLD=TRUE

### LAYERFONTSIZE

This parameter specifies the font size for rendering layer title in point.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&LAYERFONTSIZE=20
```




図 3.14: Legend with LAYERFONTSIZE=20

### LAYERFONTITALIC

This parameter specifies whether the layer title is rendered in italic. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&LAYERFONTITALIC=TRUE
```




図 3.15: Legend with LAYERFONTITALIC=TRUE

## LAYERFONTCOLOR

This parameter specifies the layer title color. The color may be literal (red, green, ..) or in hexadecimal notation (0xFF0000, 0x00FF00, ...).

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&LAYERFONTCOLOR=0x5f9930
```



図 3.16: Legend with LAYERFONTCOLOR=0x5f9930

## ITEMFONTFAMILY

This parameter specifies the font family to use for rendering item label.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries
&ITEMFONTFAMILY=monospace
```

### ITEMFONTBOLD

This parameter specifies whether the item label is rendered in bold. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&ITEMFONTBOLD=TRUE
```



図 3.17: Legend with ITEMFONTBOLD=TRUE

### ITEMFONTSIZE

This parameter specifies the font size for rendering layer title in point.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&ITEMFONTSIZE=20
```



図 3.18: Legend with ITEMFONTSIZE=30

### ITEMFONTITALIC

This parameter specifies whether the item label is rendered in italic. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?  
SERVICE=WMS  
&REQUEST=GetLegendGraphics  
&LAYERS=airports,places  
&BBOX=43.20,-2.93,49.35,8.32  
&CRS=EPSG:4326  
&TRANSPARENT=TRUE  
&ITEMFONTITALIC=TRUE
```




図 3.19: Legend with ITEMFONTITALIC=TRUE

## ITEMFONTCOLOR

This parameter specifies the item label color. The color may be literal (red, green, ..) or in hexadecimal notation (0xFF0000, 0x00FF00, ...).

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&ITEMFONTCOLOR=0x5f9930
```



図 3.20: Legend with ITEMFONTCOLOR=0x5f9930

### 3.2.5 GetStyle(s)

Standard parameters for the **GetStyle** (or **GetStyles**) request according to the OGC WMS 1.1.1 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetStyle</b> or <b>GetStyles</b> )
<i>LAYERS</i>	はい	Layers to query

The **GetStyle** request supports as well the following vendor parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
```

(次のページに続く)

(前のページからの続き)

```
&REQUEST=GetStyles
&LAYERS=mylayer1,mylayer2
```

### 3.2.6 DescribeLayer

Standard parameters for the **DescribeLayer** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>DescribeLayer</b> )
<i>LAYERS</i>	はい	Layers to describe
<i>SLD_VERSION</i>	はい	SLD version

The **DescribeLayer** request supports as well the following vendor parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=DescribeLayer
&SLD_VERSION=1.1.0
&LAYERS=mylayer1
```

The XML document looks like:

```
<DescribeLayerResponse xmlns="http://www.opengis.net/sld" xmlns:xsi="http://www.w3.
↪org/2001/XMLSchema-instance" xmlns:ows="http://www.opengis.net/ows" xmlns:xlink=
↪"http://www.w3.org/1999/xlink" xmlns:se="http://www.opengis.net/se"
↪xsi:schemaLocation="http://www.opengis.net/sld http://schemas.opengis.net/sld/1.1.0/
↪DescribeLayer.xsd">
  <Version>1.1.0</Version>
  <LayerDescription>
    <owsType>wfs</owsType>
    <se:OnlineResource xlink:href="http://localhost/qgis_server" xlink:type=
↪"simple"/>
    <TypeName>
      <se:FeatureTypeName>my_vector_layer</se:FeatureTypeName>
    </TypeName>
  </LayerDescription>
</LayerDescription>
```

(次のページに続く)

```

<owsType>wcs</owsType>
<se:OnlineResource xlink:href="http://localhost/qgis_server" xlink:type=
↪"simple"/>
  <TypeName>
    <se:FeatureTypeName>my_raster_layer</se:FeatureTypeName>
  </TypeName>
</LayerDescription>
</DescribeLayerResponse>
    
```

### SLD\_VERSION

This parameter allows to specify the version of SLD. Only the value 1.1.0 is available.

### 3.2.7 GetPrint

QGIS サーバには、PDF またはピクセル形式のプリントレイアウト出力を作成する機能があります。公表されたプロジェクトでのプリントレイアウトがテンプレートとして使用されます。GETPRINT 要求では、クライアントは含まれているレイアウト地図とラベルのパラメータを指定する可能性があります。

The **GetPrint** request supports *redlining*, *external WMS layers* as well as the following parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetPrint</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>LAYERS</i>	いいえ	Layers to display
<i>TEMPLATE</i>	はい	Layout template to use
<i>SRS / CRS</i>	はい	座標参照系
<i>FORMAT</i>	いいえ	出力形式
<i>ATLAS_PK</i>	いいえ	Atlas features
<i>STYLES</i>	いいえ	Layers' style
<i>TRANSPARENT</i>	いいえ	透明な背景
<i>OPACITIES</i>	いいえ	Opacity for layer or group
<i>SELECTION</i>	いいえ	Highlight features
<i>mapX:EXTENT</i>	いいえ	Extent of the map 'X'
<i>mapX:LAYERS</i>	いいえ	Layers of the map 'X'
<i>mapX:STYLES</i>	いいえ	Layers' style of the map 'X'
<i>mapX:SCALE</i>	いいえ	Layers' scale of the map 'X'
<i>mapX:ROTATION</i>	いいえ	Rotation of the map 'X'
<i>mapX:GRID_INTERVAL_X</i>	いいえ	Grid interval on x axis of the map 'X'
<i>mapX:GRID_INTERVAL_Y</i>	いいえ	Grid interval on y axis of the map 'X'

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetPrint
&MAP=/home/qgis/projects/world.qgs
&CRS=EPSG:4326
&FORMAT=png
&TEMPLATE=Layout%201
&map0:EXTENT=-180,-90,180,90
&map0:LAYERS=mylayer1,mylayer2,mylayer3
&map0:OPACITIES=125,200,125
&map0:ROTATION=45
```

レイアウトテンプレートには複数のマップが含まれている可能性があることに注意してください。このように、特定のマップを設定したい場合は、mapX: パラメータを使う必要があります。ここで、X は **GetProjectSettings** リクエストのおかげで取得できる正数です。

For example:

```
<WMS_Capabilities>
...
<ComposerTemplates xsi:type="wms:_ExtendedCapabilities">
<ComposerTemplate width="297" height="210" name="Druckzusammenstellung 1">
<ComposerMap width="171" height="133" name="map0"/>
<ComposerMap width="49" height="46" name="map1"/></ComposerTemplate>
</ComposerTemplates>
...
</WMS_Capabilities>
```

## TEMPLATE

This parameter can be used to specify the name of a layout template to use for printing.

## FORMAT

This parameter specifies the format of map image. Available values are:

- png (default value)
- image/png
- jpg
- jpeg
- image/jpeg

- `svg`
- `image/svg`
- `image/svg+xml`
- `pdf`
- `application/pdf`

If the `FORMAT` parameter is different from one of these values, then an exception is returned.

### **ATLAS\_PK**

This parameter allows activation of Atlas rendering by indicating which features we want to print. In order to retrieve an atlas with all features, the `*` symbol may be used (according to the maximum number of features allowed in the project configuration).

When `FORMAT` is `pdf`, a single PDF document combining the feature pages is returned. For all other formats, a single page is returned.

### **mapX:EXTENT**

This parameter specifies the extent for a layout map item as `xmin,ymin,xmax,ymax`.

### **mapX:ROTATION**

This parameter specifies the map rotation in degrees.

### **mapX:GRID\_INTERVAL\_X**

This parameter specifies the grid line density in the X direction.

### **mapX:GRID\_INTERVAL\_Y**

This parameter specifies the grid line density in the Y direction.

### mapX:SCALE

このパラメータは、レイアウト地図アイテムの地図縮尺を指定します。これは、クライアントとサーバーで縮尺分母を計算するアルゴリズムが異なる場合でもレイヤとラベルの縮尺に基づく可視性を確保するのに役立ちます。

### mapX:LAYERS

This parameter specifies the layers for a layout map item. See *GetMap Layers* for more information on this parameter.

### mapX:STYLES

This parameter specifies the layers' styles defined in a specific layout map item. See *GetMap Styles* for more information on this parameter.

## 3.2.8 GetProjectSettings

This request type works similar to *GetCapabilities*, but it is more specific to QGIS Server and allows a client to read additional information which are not available in the *GetCapabilities* output:

- レイヤーの初期可視性
- ベクターの属性とその編集タイプに関する情報
- レイヤーの順序と描画順序に関する情報
- WFS に掲載されたレイヤのリスト
- show if a group in the layer tree is mutually exclusive

The **GetProjectSettings** request supports the following parameters:

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetProjectSettings</b> )

### 3.2.9 GetSchemaExtension

The **GetSchemaExtension** request allows to retrieve optional extended capabilities and operations of the WMS service such as implemented by QGIS Server.

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>SERVICE</i>	はい	Name of the service ( <b>WMS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetSchemaExtension</b> )

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetSchemaExtension
```

The XML document looks like:

```
<schema xmlns="http://www.w3.org/2001/XMLSchema" xmlns:wms="http://www.opengis.net/wms
↳" xmlns:qgs="http://www.qgis.org/wms" targetNamespace="http://www.qgis.org/wms"
↳elementFormDefault="qualified" version="1.0.0">
  <import namespace="http://www.opengis.net/wms" schemaLocation="http://schemas.
↳opengis.net/wms/1.3.0/capabilities_1_3_0.xsd"/>
  <element name="GetPrint" type="wms:OperationType" substitutionGroup="wms:_
↳ExtendedOperation"/>
  <element name="GetStyles" type="wms:OperationType" substitutionGroup="wms:_
↳ExtendedOperation"/>
</schema>
```

### 3.2.10 External WMS layers

QGIS Server allows including layers from external WMS servers in WMS *GetMap* and WMS *GetPrint* requests. This is especially useful if a web client uses an external background layer in the web map. For performance reasons, such layers should be directly requested by the web client (not cascaded via QGIS server). For printing however, these layers should be cascaded via QGIS server in order to appear in the printed map.

External layers can be added to the *LAYERS* parameter as *EXTERNAL\_WMS:<layername>*. The parameters for the external WMS layers (e.g. url, format, dpiMode, crs, layers, styles) can later be given as service parameters *<layername>:<parameter>*. In a *GetMap* request, this might look like this:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&LAYERS=EXTERNAL_WMS:basemap,layer1,layer2
&OPACITIES=100,200,255
```

(次のページに続く)

(前のページからの続き)

```
&STYLES=,,
&basemap:url=http://externalserver.com/wms.fcgi
&basemap:format=image/jpeg
&basemap:dpiMode=7
&basemap:crs=EPSG:2056
&basemap:layers=orthofoto
&basemap:styles=default
```

Similarly, external layers can be used in *GetPrint* requests:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetPrint
&TEMPLATE=A4
&map0:layers=EXTERNAL_WMS:basemap,layer1,layer2
&map0:EXTENT=<minx,miny,maxx,maxy>
&OPACITIES=100,200,255
&basemap:url=http://externalserver.com/wms.fcgi
&basemap:format=image/jpeg
&basemap:dpiMode=7
&basemap:crs=EPSG:2056
&basemap:layers=orthofoto
&basemap:styles=default
```

### 3.2.11 Redlining

This feature is available and can be used with *GetMap* and *GetPrint* requests.

赤線引き地物は、リクエスト中のジオメトリとラベルに渡すのに使用できます、標準返された画像（地図）上でサーバーによって重ねあわされます。これにより、ユーザーは、標準地図にないいくつかの領域、場所などに強調（emphasis）またはコメント（ラベル）を追加することが可能になります。

The *GetMap* request is in the format:

```
http://localhost/qgisserver?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetMap
&HIGHLIGHT_GEOM=POLYGON((590000 5647000, 590000 6110620, 2500000 6110620, 2500000
↪5647000, 590000 5647000))
&HIGHLIGHT_SYMBOL=<StyledLayerDescriptor><UserStyle><Name>Highlight</Name>
↪<FeatureTypeStyle><Rule><Name>Symbol</Name><LineSymbolizer><Stroke><SvgParameter.
↪name="stroke">%23ea1173</SvgParameter><SvgParameter name="stroke-opacity">1</
↪SvgParameter><SvgParameter name="stroke-width">1.6</SvgParameter></Stroke></
↪LineSymbolizer></Rule></FeatureTypeStyle></UserStyle></StyledLayerDescriptor>
```

(次のページに続く)

```
&HIGHLIGHT_LABELSTRING=Write label here
&HIGHLIGHT_LABELSIZE=16
&HIGHLIGHT_LABELCOLOR=%23000000
&HIGHLIGHT_LABELBUFFERCOLOR=%23FFFFFF
&HIGHLIGHT_LABELBUFFERSIZE=1.5
```

The *GetPrint* equivalent is in the format (note that mapX: parameter is added to tell which map has redlining):

```
http://localhost/qgisserver?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetPrint
&map0:HIGHLIGHT_GEOM=POLYGON((590000 5647000, 590000 6110620, 2500000 6110620, ↵
↵2500000 5647000, 590000 5647000))
&map0:HIGHLIGHT_SYMBOL=<StyledLayerDescriptor><UserStyle><Name>Highlight</Name>
↵<FeatureTypeStyle><Rule><Name>Symbol</Name><LineSymbolizer><Stroke><SvgParameter ↵
↵name="stroke">%23ea1173</SvgParameter><SvgParameter name="stroke-opacity">1</
↵SvgParameter><SvgParameter name="stroke-width">1.6</SvgParameter></Stroke></
↵LineSymbolizer></Rule></FeatureTypeStyle></UserStyle></StyledLayerDescriptor>
&map0:HIGHLIGHT_LABELSTRING=Write label here
&map0:HIGHLIGHT_LABELSIZE=16
&map0:HIGHLIGHT_LABELCOLOR=%23000000
&map0:HIGHLIGHT_LABELBUFFERCOLOR=%23FFFFFF
&map0:HIGHLIGHT_LABELBUFFERSIZE=1.5
```

ポリゴンとラベルが通常地図の上に描かれている、上記の要求によって出力された画像は次のとおりです :



図 3.21: レッドラインパラメーターを持つ GetMap リクエストに対するサーバーの応答

このリクエストにはいくつかのパラメーターがあります。

- **HIGHLIGHT\_GEOM**: You can add POINT, MULTILINESTRING, POLYGON etc. It supports multi-part geometries. Here is an example: `HIGHLIGHT_GEOM=MULTILINESTRING((0 0, 0 1, 1 1))`. The coordinates should be in the CRS of the GetMap/GetPrint request.
- **HIGHLIGHT\_SYMBOL** : ジオメトリの輪郭をどのように表示するかを制御し、ストロークの幅、色、不透明度を変更できます。
- **HIGHLIGHT\_LABELSTRING** : ラベルのテキストをこのパラメーターに渡すことができます。
- **HIGHLIGHT\_LABELSIZE**: このパラメーターは、ラベルのサイズを制御します。
- **HIGHLIGHT\_LABELFONT**: This parameter controls the font of the label (e.g. Arial)
- **HIGHLIGHT\_LABELCOLOR**: このパラメーターは、ラベルの色を制御します。
- **HIGHLIGHT\_LABELBUFFERCOLOR**: このパラメーターは、ラベルバッファの色を制御します。
- **HIGHLIGHT\_LABELBUFFERSIZE**: このパラメーターは、ラベルバッファのサイズを制御します。

## 3.3 Web Feature Service (WFS)

The **1.0.0** and **1.1.0** WFS standards implemented in QGIS Server provide a HTTP interface to query geographic features from a QGIS project. A typical WFS request defines the QGIS project to use and the layer to query.

Specifications document according to the version number of the service:

- WFS 1.0.0
- WFS 1.1.0

Standard requests provided by QGIS Server:

Request	説明
<i>GetCapabilities</i>	Returns XML metadata with information about the server
<i>GetFeature</i>	Returns a selection of features
<i>DescribeFeatureType</i>	Returns a description of feature types and properties
<i>Transaction</i>	Allows features to be inserted, updated or deleted

### 3.3.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WFS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetCapabilities</b> )
<i>VERSION</i>	いいえ	Version of the service

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

#### VERSION

This parameter allows to specify the version of the service to use. Available values for the **VERSION** parameter are:

- 1.0.0
- 1.1.0

If no version is indicated in the request, then 1.1.0 is used by default.

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&...
```

### 3.3.2 GetFeature

Standard parameters for the **GetFeature** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WFS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetFeature</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>TYPENAME</i>	いいえ	レイヤの名前
<i>FEATUREID</i>	いいえ	Filter the features by ids
<i>OUTPUTFORMAT</i>	いいえ	Output Format
<i>RESULTTYPE</i>	いいえ	Type of the result
<i>PROPERTYNAME</i>	いいえ	Name of properties to return
<i>MAXFEATURES</i>	いいえ	Maximum number of features to return
<i>SRSNAME</i>	いいえ	座標参照系
<i>FILTER</i>	いいえ	OGC Filter Encoding
<i>BBOX</i>	いいえ	Map Extent
<i>SORTBY</i>	いいえ	Sort the results

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>STARTINDEX</i>	いいえ	Paging
<i>GEOMETRYNAME</i>	いいえ	Type of geometry to return
<i>EXP_FILTER</i>	いいえ	Expression filtering

#### TYPENAME

This parameter allows to specify layer names and is mandatory if **FEATUREID** is not set.

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=GetFeature
&TYPENAME=countries
```

## FEATUREID

This parameter allows to specify the ID of a specific feature and is formed like `typename.fid`, `typename.fid`,  
....

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&REQUEST=GetFeature  
&FEATUREID=countries.0,places.1
```

XML response:

```
<wfs:FeatureCollection xmlns:wfs="http://www.opengis.net/wfs" xmlns:ogc="http://www.  
↪opengis.net/ogc" xmlns:gml="http://www.opengis.net/gml" xmlns:ows="http://www.  
↪opengis.net/ows" xmlns:xlink="http://www.w3.org/1999/xlink" xmlns:qgs="http://www.  
↪qgis.org/gml" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" ↪  
↪xsi:schemaLocation="http://www.opengis.net/wfs http://schemas.opengis.net/wfs/1.1.0/  
↪wfs.xsd http://www.qgis.org/gml http://192.168.1.15/qgisserver?SERVICE=WFS&  
↪VERSION=1.1.0&REQUEST=DescribeFeatureType&TYPENAME=countries,places&  
↪OUTPUTFORMAT=text/xml; subtype%3Dgml/3.1.1">  
  <gml:boundedBy>  
    ...  
  </gml:boundedBy>  
  <gml:featureMember>  
    <qgs:countries gml:id="countries.1">  
      ...  
    </qgs:countries>  
  </gml:featureMember>  
  <gml:featureMember>  
    <qgs:places gml:id="places.1">  
      ...  
    </qgs:places>  
  </gml:featureMember>  
</wfs:FeatureCollection>
```

## OUTPUTFORMAT

This parameter may be used to specify the format of the response. If `VERSION` is greater or equal than `1.1.0`, GML3 is the default format. Otherwise GML2 is used.

Available values are:

- gml2
- text/xml; subtype=gml/2.1.2

- gml3
- text/xml; subtype=gml/3.1.1
- geojson
- application/vnd.geo+json,
- application/vnd.geo json
- application/geo+json
- application/geo json
- application/json

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&REQUEST=GetFeature  
&FEATUREID=countries.0  
&OUTPUTFORMAT=geojson
```

GeoJSON response:

```
{  
  "type": "FeatureCollection",  
  "bbox": [  
    -180,  
    -90,  
    180,  
    83.6236  
  ],  
  "features": [  
    {  
      "bbox": [  
        -61.891113,  
        16.989719,  
        -61.666389,  
        17.724998  
      ],  
      "geometry": {  
        "coordinates": [  
          "..."  
        ],  
        "type": "MultiPolygon"  
      },  
      "id": "countries.1",  
      "properties": {
```

(次のページに続く)

```

        "id":1,
        "name":"Antigua and Barbuda"
    },
    "type":"Feature"
}
]
}

```

## RESULTTYPE

This parameter may be used to specify the kind of result to return. Available values are:

- **results**: the default behavior
- **hits**: returns only a feature count

URL example:

```

http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=GetFeature
&RESULTTYPE=hits
&...

```

## PROPERTYNAME

This parameter may be used to specify a specific property to return. A property needs to be mapped with a TYPENAME or a FEATUREID:

Valid URL example:

```

http://localhost/qgisserver?
SERVICE=WFS
&REQUEST=GetFeature
&PROPERTYNAME=name
&TYPENAME=places

```

On the contrary, the next URL will return an exception:

```

http://localhost/qgisserver?
SERVICE=WFS
&REQUEST=GetFeature
&PROPERTYNAME=name
&TYPENAME=places,countries

```

```
<ServiceExceptionReport xmlns="http://www.opengis.net/ogc" version="1.2.0">
  <ServiceException code="RequestNotWellFormed">There has to be a 1:1 mapping
  ↪ between each element in a TYPENAME and the PROPERTYNAME list</ServiceException>
</ServiceExceptionReport>
```

## MAXFEATURES

This parameter allows to limit the number of features returned by the request.

注釈: This parameter may be useful to improve performances when underlying vector layers are heavy.

## SRSNAME

This parameter allows to indicate the response output Spatial Reference System as well as the BBOX CRS and has to be formed like EPSG:XXXX.

```
http://localhost/qgisserver?
SERVICE=WFS
&REQUEST=GetFeature
&TYPENAME=places
&SRSNAME=EPSG:32620
```

## FILTER

This parameter allows to filter the response with the **Filter Encoding** language defined by the [OGC Filter Encoding standard](#).

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS&
REQUEST=GetFeature&
TYPENAME=places&
FILTER=<Filter><PropertyIsEqualTo><PropertyName>name</PropertyName><Literal>Paris</
  ↪ Literal></PropertyIsEqualTo></Filter>
```

### BBOX

This parameter allows to specify the map extent with units according to the current CRS. Coordinates have to be separated by a comma.

The SRSNAME parameter may specify the CRS of the extent. If not specified, the CRS of the layer is used.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&REQUEST=GetFeature  
&TYPENAME=places  
&BBOX=-11.84,42.53,8.46,50.98
```

The FEATUREID parameter cannot be used with the BBOX. Any attempt will result in an exception:

```
<ServiceExceptionReport xmlns="http://www.opengis.net/ogc" version="1.2.0">  
  <ServiceException code="RequestNotWellFormed">FEATUREID FILTER and BBOX parameters  
  →are mutually exclusive</ServiceException>  
</ServiceExceptionReport>
```

### SORTBY

This parameter allows to sort resulting features according to property values and has to be formed like propertyname SORTRULE.

Available values for SORTRULE in case of descending sorting:

- D
- +D
- DESC
- +DESC

Available values for SORTRULE in case of ascending sorting:

- A
- +A
- ASC
- +ASC

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&REQUEST=GetFeature
```

(次のページに続く)

(前のページからの続き)

```
&TYPENAME=places
&PROPERTYNAME=name
&MAXFEATURES=3
&SORTBY=name DESC
```

The corresponding result:

```
<wfs:FeatureCollection xmlns:wfs="http://www.opengis.net/wfs" xmlns:ogc="http://www.
↳opengis.net/ogc" xmlns:gml="http://www.opengis.net/gml" xmlns:ows="http://www.
↳opengis.net/ows" xmlns:xlink="http://www.w3.org/1999/xlink" xmlns:qgs="http://www.
↳qgis.org/gml" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
↳xsi:schemaLocation="http://www.opengis.net/wfs http://schemas.opengis.net/wfs/1.1.0/
↳wfs.xsd http://www.qgis.org/gml http://192.168.1.15/qgisserver?SERVICE=WFS&
↳VERSION=1.1.0&REQUEST=DescribeFeatureType&TYPENAME=places&OUTPUTFORMAT=text/xml;
↳subtype%3Dgml/3.1.1">
  <gml:boundedBy>
    ...
  </gml:boundedBy>
  <gml:featureMember>
    <qgs:places gml:id="places.90">
      <qgs:name>Zagreb</qgs:name>
    </qgs:places>
  </gml:featureMember>
  <gml:featureMember>
    <qgs:places gml:id="places.113">
      <qgs:name>Yerevan</qgs:name>
    </qgs:places>
  </gml:featureMember>
  <gml:featureMember>
    <qgs:places gml:id="places.111">
      <qgs:name>Yaounde</qgs:name>
    </qgs:places>
  </gml:featureMember>
</wfs:FeatureCollection>
```

## GEOMETRYNAME

このパラメータは、地物に返すジオメトリの種類を指定するために使用できます。利用可能な値は以下のとおりです：

- 範囲
- 重心
- none

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&VERSION=1.1.0  
&REQUEST=GetFeature  
&GEOMETRYNAME=centroid  
&...
```

### STARTINDEX

This parameter is standard in WFS 2.0, but it's an extension for WFS 1.0.0.

Actually, it can be used to skip some features in the result set and in combination with **MAXFEATURES**, it provides the ability to page through results.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS  
&VERSION=1.1.0  
&REQUEST=GetFeature  
&STARTINDEX=2  
&...
```

### EXP\_FILTER

This parameter allows to filter the response with QGIS expressions.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WFS&  
REQUEST=GetFeature&  
TYPENAME=places&  
EXP_FILTER="name"='Paris'
```

### 3.3.3 DescribeFeatureType

Standard parameters for the **DescribeFeatureType** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WFS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>DescribeFeatureType</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>OUTPUTFORMAT</i>	いいえ	Format of the response
<i>TYPENAME</i>	いいえ	レイヤの名前

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=DescribeFeatureType
&TYPENAME=countries
```

Output response:

```
<schema xmlns:ogc="http://www.opengis.net/ogc" xmlns:xsd="http://www.w3.org/2001/
↵XMLSchema" xmlns="http://www.w3.org/2001/XMLSchema" xmlns:qgs="http://www.qgis.org/
↵gml" xmlns:gml="http://www.opengis.net/gml" targetNamespace="http://www.qgis.org/gml
↵" version="1.0" elementFormDefault="qualified">
  <import schemaLocation="http://schemas.opengis.net/gml/3.1.1/base/gml.xsd"
↵namespace="http://www.opengis.net/gml"/>
  <element type="qgs:countriesType" substitutionGroup="gml:_Feature" name="countries"/
↵>
  <complexType name="countriesType">
    <complexContent>
      <extension base="gml:AbstractFeatureType">
        <sequence>
          <element minOccurs="0" type="gml:MultiPolygonPropertyType" maxOccurs="1"
↵name="geometry"/>
          <element type="long" name="id"/>
          <element nillable="true" type="string" name="name"/>
        </sequence>
      </extension>
    </complexContent>
  </complexType>
</schema>
```

(次のページに続く)

```
</complexContent>
</complexType>
</schema>
```

### 3.3.4 Transaction

This request allows to update, delete or add one or several features thanks to a XML document. The *delete* action may be achieved with a POST request as well as with the *OPERATION* parameter while the *add* and the *update* operations may be achieved through POST request only.

Standard parameters for the **Transaction** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WFS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>Transaction</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>FILTER</i>	いいえ	OGC Filter Encoding
<i>BBOX</i>	いいえ	Map Extent
<i>FEATUREID</i>	いいえ	Filter the features by ids
<i>TYPENAME</i>	いいえ	レイヤの名前

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file
<i>OPERATION</i>	いいえ	Specify the operation
<i>EXP_FILTER</i>	いいえ	Expression filtering

#### OPERATION

This parameter allows to delete a feature without using a POST request with a dedicated XML document.

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=Transaction
&OPERATION=DELETE
&FEATUREID=24
```

注釈: FEATUREID, BBOX and FILTER parameters are mutually exclusive and prioritized in this order.

## Add features

POST request example:

```
wget --post-file=add.xml "http://localhost/qgisserver?SERVICE=WFS&REQUEST=Transaction"
```

with the *add.xml* document:

```
<?xml version="1.0" encoding="UTF-8"?>
<wfs:Transaction service="WFS" version="1.0.0" xmlns:wfs="http://www.opengis.net/wfs"
↳xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:ogc="http://www.opengis.
↳net/ogc" xmlns="http://www.opengis.net/wfs" updateSequence="0" xmlns:xlink="http://
↳www.w3.org/1999/xlink" xsi:schemaLocation="http://www.opengis.net/wfs http://
↳schemas.opengis.net/wfs/1.0.0/WFS-capabilities.xsd" xmlns:gml="http://www.opengis.
↳net/gml" xmlns:ows="http://www.opengis.net/ows">
  <wfs:Insert idgen="GenerateNew">
    <qgs:places>
      <qgs:geometry>
        <gml:Point srsDimension="2" srsName="http://www.opengis.net/def/crs/EPSG/0/
↳4326">
          <gml:coordinates decimal="." cs="," ts=" ">-4.6167,48.3833</gml:coordinates>
        </gml:Point>
      </qgs:geometry>
      <qgs:name>Locmaria-Plouzané</qgs:name>
    </qgs:places>
  </wfs:Insert>
</wfs:Transaction>
```

## Update features

POST request example:

```
wget --post-file=update.xml "http://localhost/qgisserver?SERVICE=WFS&
↳REQUEST=Transaction"
```

with the *update.xml* document:

```
<?xml version="1.0" encoding="UTF-8"?>
<wfs:Transaction service="WFS" version="1.0.0" xmlns:wfs="http://www.opengis.net/wfs"
↳xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:ogc="http://www.opengis.
↳net/ogc" xmlns="http://www.opengis.net/wfs" updateSequence="0" xmlns:xlink="http://
↳www.w3.org/1999/xlink" xsi:schemaLocation="http://www.opengis.net/wfs http://www.opengis.
↳schemas.opengis.net/wfs/1.0.0/WFS-capabilities.xsd" xmlns:gml="http://www.opengis.
↳net/gml" xmlns:ows="http://www.opengis.net/ows">
  <wfs:Update idgen="GenerateNew">
    <qgs:places>
      <qgs:geometry>
        <gml:Point srsDimension="2" srsName="http://www.opengis.net/def/crs/EPSG/0/
↳4326">
          <gml:coordinates decimal="." cs="," ts=" ">-4.6167,48.3833</gml:coordinates>
        </gml:Point>
      </qgs:geometry>
      <qgs:name>Locmaria-Plouzané</qgs:name>
    </qgs:places>
  </wfs:Update>
</wfs:Transaction>
```

```
<wfs:Update typeName="places">
  <wfs:Property>
    <wfs:Name>name</wfs:Name>
    <wfs:Value>Lutece</wfs:Value>
  </wfs:Property>
  <ogc:Filter>
    <ogc:FeatureId fid="24"/>
  </ogc:Filter>
</wfs:Update>
</wfs:Transaction>
```

### Delete features

POST request example:

```
wget --post-file=delete.xml "http://localhost/qgisserver?SERVICE=WFS&
↳REQUEST=Transaction"
```

with the *delete.xml* document:

```
<?xml version="1.0" encoding="UTF-8"?>
<wfs:Transaction service="WFS" version="1.0.0" xmlns:wfs="http://www.opengis.net/wfs"
↳xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:ogc="http://www.opengis.
↳net/ogc" xmlns="http://www.opengis.net/wfs" updateSequence="0" xmlns:xlink="http://
↳www.w3.org/1999/xlink" xsi:schemaLocation="http://www.opengis.net/wfs http://
↳schemas.opengis.net/wfs/1.0.0/WFS-capabilities.xsd" xmlns:gml="http://www.opengis.
↳net/gml" xmlns:ows="http://www.opengis.net/ows">
  <wfs>Delete typeName="places">
    <ogc:Filter>
      <ogc:FeatureId fid="24"/>
    </ogc:Filter>
  </wfs>Delete>
</wfs:Transaction>
```

## 3.4 Web Coverage Service (WCS)

The 1.0.0 and 1.1.1 WCS standards implemented in QGIS Server provide a HTTP interface to access raster data, referred to as *coverage*, coming from a QGIS project.

Specifications:

- WCS 1.0.0
- WCS 1.1.1

Standard requests provided by QGIS Server:

Request	説明
<i>GetCapabilities</i>	Returns XML metadata with information about the server
<i>DescribeCoverage</i>	Retrieves XML document about additional information about coverages
<i>GetCoverage</i>	Retrieves coverage

### 3.4.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WCS 1.1.1 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WCS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetCapabilities</b> )
<i>VERSION</i>	いいえ	Version of the service

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/qgis_server?
SERVICE=WCS
&VERSION=1.1.1
&REQUEST=GetCapabilities
```

XML document example when a single raster layer (named T20QPD\_20171123T144719\_TCI) is published in the QGIS project for the WCS service:

```
<WCS_Capabilities xmlns="http://www.opengis.net/wcs" xmlns:xlink="http://www.w3.org/
↪1999/xlink" xmlns:gml="http://www.opengis.net/gml" xmlns:xsi="http://www.w3.org/
↪2001/XMLSchema-instance" version="1.0.0" updateSequence="0" xsi:schemaLocation=
↪"http://www.opengis.net/wcs http://schemas.opengis.net/wcs/1.0.0/wcsCapabilities.xsd
↪">
  <Service>
    ...
  </Service>
  <Capability>
    ...
  </Capability>
  <ContentMetadata>
    <CoverageOfferingBrief>
```

(次のページに続く)

```

<name>T20QPD_20171123T144719_TCI</name>
<label>T20QPD_20171123T144719_TCI</label>
<lonLatEnvelope srsName="urn:ogc:def:crs:OGC:1.3:CRS84">
  <gml:pos>-61.585973 16.331189</gml:pos>
  <gml:pos>-61.52537 16.400376</gml:pos>
</lonLatEnvelope>
</CoverageOfferingBrief>
</ContentMetadata>
</WCS_Capabilities>

```

## VERSION

This parameter allows to specify the version of the service to use. Currently, the version values is not internally used and always fallback to 1.1.1.

### 3.4.2 DescribeCoverage

This request allows to retrieve additional information about coverages like the format of the underlying datasource, the number of bands, ... Standard parameters for the **DescribeCoverage** request according to the OGC WCS 1.1.1 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WCS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>DescribeCoverage</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>COVERAGE</i>	いいえ	Specify coverage layers (WCS 1.0.0)
<i>IDENTIFIER</i>	いいえ	Specify coverage layers (WCS 1.1.1)

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

The XML document for a 3 bands GeoTIFF raster layer looks like:

```

<CoverageDescription xmlns:xlink="http://www.w3.org/1999/xlink" xmlns="http://www.
↪opengis.net/wcs" xmlns:gml="http://www.opengis.net/gml" xmlns:xsi="http://www.w3.
↪org/2001/XMLSchema-instance" updateSequence="0" version="1.0.0" xsi:schemaLocation=
↪"http://www.opengis.net/wcs http://schemas.opengis.net/wcs/1.0.0/DescribeCoverage.
↪xsd">
  <CoverageOffering>

```

(前のページからの続き)

```

<name>T20QPD_20171123T144719_TCI</name>
<label>T20QPD_20171123T144719_TCI</label>
<lonLatEnvelope srsName="urn:ogc:def:crs:OGC:1.3:CRS84">
  ...
</lonLatEnvelope>
<domainSet>
  ...
</domainSet>
<rangeSet>
  <RangeSet>
    <name>Bands</name>
    <label>Bands</label>
    <axisDescription>
      <AxisDescription>
        <name>bands</name>
        <label>bands</label>
        <values>
          <singleValue>1</singleValue>
          <singleValue>2</singleValue>
          <singleValue>3</singleValue>
        </values>
      </AxisDescription>
    </axisDescription>
  </RangeSet>
</rangeSet>
<supportedCRSs>
  ...
</supportedCRSs>
<supportedFormats nativeFormat="raw binary">
  <formats>GeoTIFF</formats>
</supportedFormats>
</CoverageOffering>
</CoverageDescription>

```

## COVERAGE

This parameter, defined in WCS 1.0.0, allows to specify the layers to query for additional information. Names have to be separated by a comma.

In addition, QGIS Server introduced an option to select layers by its short name. The short name of a layer may be configured through *Properties* → *Metadata* in layer menu. If the short name is defined, then it's used by default instead of the layer's name:

```
http://localhost/qgisserver?
SERVICE=WCS
&REQUEST=DescribeCoverage
&COVERAGE=mylayer1name,mylayer2shortname
```

注釈: COVERAGE is mandatory if IDENTIFIER is not set.

## IDENTIFIER

This parameter replaces the *COVERAGE* parameter in WCS 1.1.1. But QGIS Server does not filter according to the *VERSION* parameter so *IDENTIFIER* and *COVERAGE* have the same effect.

注釈: *IDENTIFIER* is mandatory if *COVERAGE* is not set. If both *IDENTIFIER* and *COVERAGE* parameters are defined, *COVERAGE* is always used in priority.

### 3.4.3 GetCoverage

This request allows to retrieve the coverage according to specific constraints like the extent or the CRS. Standard parameters for the **DescribeCoverage** request according to the OGC WCS 1.1.1 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WCS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetCoverage</b> )
<i>VERSION</i>	いいえ	Version of the service
<i>COVERAGE</i>	いいえ	Specify coverage layers (WCS 1.0.0)
<i>IDENTIFIER</i>	いいえ	Specify coverage layers (WCS 1.1.1)
<i>WIDTH</i>	はい	Width of the response in pixels
<i>HEIGHT</i>	はい	Height of the response in pixels
<i>BBOX</i>	はい	Map extent in CRS units
<i>CRS</i>	はい	Coordinate reference system of the extent
<i>RESPONSE_CRS</i>	いいえ	Coordinate reference system of the response

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

## BBOX

This parameter allows to specify the map extent in the units of the current CRS. Coordinates have to be separated by a comma. The BBOX parameter is formed like `minx,miny,maxx,maxy`.

URL example:

```
http://localhost/qgisserver?  
SERVICE=WCS  
&REQUEST=GetCoverage  
&IDENTIFIER=T20QPD_20171123T144719_TCI  
&BBOX=647533,1805950,660987,1813940  
&CRS=EPSG:32620
```

## CRS

This parameter allows to indicate the Spatial Reference System of the BBOX parameter and has to be formed like `EPSG:XXXX`.

## RESPONSE\_CRS

This parameter allows to indicate the output response Spatial Reference System and has to be formed like `EPSG:XXXX`. The CRS of the corresponding coverage layer is used by default.

## WIDTH

This parameter allows to specify the width in pixels of the output image. The resolution of the response image depends on this value.

## HEIGHT

This parameter allows to specify the height in pixels of the output image. The resolution of the response image depends on this value.




図 3.22: From left to right: WIDTH=20&HEIGHT=20, WIDTH=50&HEIGHT=50, WIDTH=100&HEIGHT=100

## 3.5 Web Map Tile Service (WMTS)

QGIS サーバに実装された **1.0.0** WMTS 標準は、QGIS プロジェクトから作成されたタイル地図画像を要求するための HTTP インターフェースを提供します。典型的な WMTS リクエストでは、使用する QGIS プロジェクト、レンダリングするレイヤなどの一部の WMS パラメータ、およびタイルパラメータを定義しました。

Specifications document of the service:

- [WMTS 1.0.0](#)

Standard requests provided by QGIS Server:

Request	説明
<i>GetCapabilities</i>	Returns XML metadata with information about the server
<i>GetTile</i>	Returns a tile
<i>GetFeatureInfo</i>	Retrieves data (geometry and values) for a pixel location

### 3.5.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WMTS 1.0.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMTS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetCapabilities</b> )

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/?
SERVICE=WMTS
&REQUEST=GetCapabilities
&MAP=/home/qgis/projects/world.qgs
```

### 3.5.2 GetTile

Standard parameters for the **GetTile** request according to the OGC WMTS 1.0.0 specifications:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMTS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetTile</b> )
<i>LAYER</i>	はい	Layer identifier
<i>FORMAT</i>	はい	Output format of the tile
<i>TILEMATRIXSET</i>	はい	Name of the pyramid
<i>TILEMATRIX</i>	はい	Meshing
<i>TILEROW</i>	はい	Row coordinate in the mesh
<i>TILECOL</i>	はい	Column coordinate in the mesh

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/?
SERVICE=WMTS
&REQUEST=GetTile
&MAP=/home/qgis/projects/world.qgs
&LAYER=mylayer
&FORMAT=image/png
&TILEMATRIXSET=EPSG:4326
&TILEROW=0
&TILECOL=0
```

### FORMAT

This parameter may be used to specify the format of tile image. Available values are:

- jpg
- jpeg
- image/jpeg
- image/png

If the FORMAT parameter is different from one of these values, then the default format PNG is used instead.

### TILEMATRIXSET

This parameter defines the CRS to use when computing the underlying pyramid. Format: EPSG:XXXX.

### TILEMATRIX

This parameter allows to define the matrix to use for the output tile.

### TILEROW

This parameter allows to select the row of the tile to get within the matrix.

### TILECOL

This parameter allows to select the column of the tile to get within the matrix.

### 3.5.3 GetFeatureInfo

Standard parameters for the **GetFeatureInfo** request according to the OGC WMTS 1.0.0 specification:

パラメーター	必須	説明
<i>SERVICE</i>	はい	Name of the service ( <b>WMTS</b> )
<i>REQUEST</i>	はい	Name of the request ( <b>GetFeatureInfo</b> )
<i>LAYER</i>	はい	Layer identifier
<i>INFOFORMAT</i>	いいえ	出力形式
<i>I</i>	いいえ	X coordinate of a pixel
<i>J</i>	いいえ	Y coordinate of a pixel
<i>TILEMATRIXSET</i>	はい	Name of the pyramid
<i>TILEMATRIX</i>	Meshing	
<i>TILEROW</i>	はい	Row coordinate in the mesh
<i>TILECOL</i>	はい	Column coordinate in the mesh

標準のものに加えて、QGIS サーバーでは以下の追加パラメータをサポートしています：

パラメーター	必須	説明
<i>MAP</i>	はい	QGIS project file

URL example:

```
http://localhost/?
SERVICE=WMTS
&REQUEST=GetFeatureInfo
&MAP=/home/qgis/projects/world.qgs
&LAYER=mylayer
&INFOFORMAT=image/html
&I=10
&J=5
```

## INFOFORMAT

This parameter allows to define the output format of the result. Available values are:

- text/xml
- text/html
- text/plain
- application/vnd.ogc.gml

The default value is text/plain.

### I

This parameter allows to define the X coordinate of the pixel for which we want to retrieve underlying information.

### J

This parameter allows to define the Y coordinate of the pixel for which we want to retrieve underlying information.

## 3.6 OGC API Features

OGC API Features (OAPIF) is the first implementation of the new generation of OGC protocols. It is described by the [OGC API - Features - Part 1: Core](#) document.

Here is a quick informal summary of the most important differences between the well known WFS protocol and OAPIF:

- OAPIF is based on a [REST API](#)
- OAPIF must follow the [OPENAPI](#) specifications
- OAPIF supports multiple output formats but it does not dictate any (only GeoJSON and HTML are currently available in QGIS OAPIF) and it uses [content negotiation](#) to determine which format is to be served to the client
- JSON and HTML are first class citizens in OAPIF
- OAPIF is self-documenting (through the `/api` endpoint)
- OAPIF is fully navigable (through links) and browsable

---

**重要:** While the OGC API Features implementation in QGIS can make use of the `MAP` parameter to specify the project file, no extra query parameters are allowed by the [OPENAPI](#) specification. For this reason it is strongly recommended that `MAP` is not exposed in the URL and the project file is specified in the environment by other means (i.e. setting `QGIS_PROJECT_FILE` in the environment through a web server rewrite rule).

---

---

**注釈:** The `API` endpoint provides comprehensive documentation of all supported parameters and output formats of your service. The following paragraphs will only describe the most important ones.

---

### 3.6.1 Resource representation

The implementation of OGC API Features in QGIS Server currently supports the following resource representation (output) formats:

- HTML
- JSON

The format that is actually served will depend on content negotiation, but a specific format can be explicitly requested by appending a format specifier to the endpoints.

Supported format specifier extensions are:

- .json
- .html

Additional format specifier aliases may be defined by specific endpoints:

- .openapi: alias for .json supported by the **API** endpoint
- .geojson: alias for .json supported by the **Features** and **Feature** endpoints

### 3.6.2 Endpoints

The API provides a list of endpoints that the clients can retrieve. The system is designed in such a way that every response provides a set of links to navigate through all the provided resources.


Endpoints provided by the QGIS implementation are:

名前	Path	説明
Landing Page	/	General information about the service and provides links to all available endpoints
Conformance	/conformance	Information about the conformance of the service to the standards
API	/api	Full description of the endpoints provided by the service and the returned documents structure
Collections	/collections	List of all collections (i.e. 'vector layers') provided by the service
Collection	/collections/{collectionId}	Information about a collection (name, metadata, extent etc.)
QGIS の主な機能	/collections/{collectionId}/items	List of the features provided by the collection
Feature	/collections/{collectionId}/items/{featureId}	Information about a single feature

### Landing Page

The main endpoint is the **Landing Page**. From that page it is possible to navigate to all the available service endpoints. The **Landing Page** must provide links to

- the API definition (path `/api` link relations `service-desc` and `service-doc`),
- the Conformance declaration (path `/conformance`, link relation `conformance`), and
- the Collections (path `/collections`, link relation `data`).



☒ 3.23: Server OAPIF landing page

### API Definition

The **API Definition** is an OPENAPI-compliant description of the API provided by the service. In its HTML representation it is a browsable page where all the endpoints and their response formats are accurately listed and documented. The path of this endpoint is `/api`.

The API definition provides a comprehensive and authoritative documentation of the service, including all supported parameters and returned formats.


---

**注釈:** This endpoint is analogue to WFS's `GetCapabilities`

---

### Collections list

The collections endpoint provides a list of all the collections available in the service. Since the service "serves" a single QGIS project the collections are the vector layers from the current project (if they were published as WFS in the project properties). The path of this endpoint is `/collections/`.




☒ 3.24: Server OAPIF collections list page

### Collection detail

While the collections endpoint does not provide detailed information about each available collection, that information is available in the `/collections/{collectionId}` endpoints. Typical information includes the extent, a description, CRSs and other metadata.

The HTML representation also provides a browsable map with the available features.



☒ 3.25: Server OAPIF collection detail page

## Features list

This endpoint provides a list of all features in a collection knowing the collection ID. The path of this endpoint is `/collections/{collectionId}/items`.

The HTML representation also provides a browsable map with the available features.

注釈: This endpoint is analogue to `GetFeature` in WFS 1 and WFS 2.




図 3.26: Server OAPIF features list page

## Feature detail

This endpoint provides all the available information about a single feature, including the feature attributes and its geometry. The path of this endpoint is `/collections/{collectionId}/items/{itemId}`.

The HTML representation also provides a browsable map with the feature geometry.

## world - feature 20

AREA	845942
FIPS	BR
ISO2	BR
ISO3	BRA
LAT	-10.772
LON	-53.089
NAME	Brazil
POP2005	186830759
REGION	19
SUBREGION	5
UN	76



powered by **QGIS Server**

図 3.27: Server OAPIF feature detail page

### 3.6.3 Pagination

Pagination of a long list of features is implemented in the OGC API through `next` and `prev` links, QGIS server constructs these links by appending `limit` and `offset` as query string parameters.

URL example:

```
http://localhost/qgisserver/oapif/collection_one/items.json?offset=10&limit=10
```

注釈: The maximum acceptable value for `limit` can be configured with the `QGIS_SERVER_API_WFS3_MAX_LIMIT` server configuration setting (see: 環境変数).

### 3.6.4 地物フィルタリング

The features available in a collection can be filtered/searched by specifying one or more filters.

### Date and time filter

Collections with date and/or datetime attributes can be filtered by specifying a `datetime` argument in the query string. By default the first date/datetime field is used for filtering. This behavior can be configured by setting a "Date" or "Time" dimension in the *QGIS Server Dimension* section of the layer properties dialog.

The date and time filtering syntax is fully described in the *API Definition* and also supports ranges (begin and end values are included) in addition to single values.

URL examples:

Returns only the features with date dimension matching 2019-01-01

```
http://localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01
```

Returns only the features with datetime dimension matching 2019-01-01T01:01:01

```
http://localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01T01:01:01
```

Returns only the features with datetime dimension in the range 2019-01-01T01:01:01 - 2019-01-01T12:00:00

```
http://localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01T01:01:01/2019-01-01T12:00:00
```

### Bounding box filter

A bounding box spatial filter can be specified with the `bbox` parameter:

The order of the comma separated elements is:

- Lower left corner, WGS 84 longitude
- Lower left corner, WGS 84 latitude
- Upper right corner, WGS 84 longitude
- Upper right corner, WGS 84 latitude

---

**注釈:** The OGC specifications also allow a 6 item `bbox` specifier where the third and sixth items are the Z components, this is not yet supported by QGIS server.

---

URL example:

```
http://localhost/qgisserver/oapif/collection_one/items.json?bbox=-180,-90,180,90
```

If the *CRS* of the bounding box is not **WGS 84**, a different *CRS* can be specified by using the optional parameter `bbox-crs`. The *CRS* format identifier must be in the **OGC URI** format:

URL example:

```
http://localhost/qgisserver/oapif/collection_one/items.json?bbox=913191,5606014,
↪913234,5606029&bbox-crs=http://www.opengis.net/def/crs/EPSG/9.6.2/3857
```

### Attribute filters

Attribute filters can be combined with the bounding box filter and they are in the general form: <attribute name>=<attribute value>. Multiple filters can be combined using the AND operator.

URL example:

filters all features where attribute name equals "my value"

```
http://localhost/qgisserver/oapif/collection_one/items.json?attribute_one=my%20value
```

Partial matches are also supported by using a \* ("star") operator:

URL example:

filters all features where attribute name ends with "value"

```
http://localhost/qgisserver/oapif/collection_one/items.json?attribute_one=*value
```

### 3.6.5 Feature sorting

It is possible to order the result set by field value using the `orderby` query parameter.

The results are sorted in ascending order by default. To sort the results in descending order, a boolean flag (`sortdesc`) can be set:

```
http://localhost/qgisserver/oapif/collection_one/items.json?orderby=name&sortdesc=1
```

### 3.6.6 Attribute selection

The feature attributes returned by a *Features list* call can be limited by adding a comma separated list of attribute names in the optional `properties` query string argument.

URL example:

returns only the name attribute

```
http://localhost/qgisserver/oapif/collection_one/items.json?properties=name
```

### 3.6.7 Customize the HTML pages

The HTML representation uses a set of HTML templates to generate the response. The template is parsed by a template engine called `inja`. The templates can be customized by overriding them (see: *Template overrides*). The template has access to the same data that are available to the JSON representation and a few additional functions are available to the template:

#### Custom template functions

- `path_append( path )`: appends a directory path to the current url
- `path_chomp( n )`: removes the specified number "n" of directory components from the current url path
- `json_dump( )`: prints the JSON data passed to the template
- `static( path )`: returns the full URL to the specified static path. For example: "`static( "/style/black.css" )`" with a root path "`http://localhost/qgisserver/oapif`" will return "`http://localhost/qgisserver/oapif/static/style/black.css`".
- `links_filter( links, key, value )`: Returns filtered links from a link list
- `content_type_name( content_type )`: Returns a short name from a content type, for example "`text/html`" will return "HTML"
- `nl2br( text )`: Returns the input text with all newlines replaced by "`<br>`" tags

#### Template overrides

Templates and static assets are stored in subdirectories of the QGIS server default API resource directory (`/usr/share/qgis/resources/server/api/` on a Linux system), the base directory can be customized by changing the environment variable `QGIS_SERVER_API_RESOURCES_DIRECTORY`.

A typical Linux installation will have the following directory tree:

```

/usr/share/qgis/resources/server/api/
  ogc
    schema.json
  static
    jsonFormatter.min.css
    jsonFormatter.min.js
    style.css
  templates
    wfs3
      describeCollection.html
      describeCollections.html
      footer.html
      getApiDescription.html
      getFeature.html
  
```

(次のページに続く)

(前のページからの続き)

```
getFeatures.html
getLandingPage.html
getRequirementClasses.html
header.html
leaflet_map.html
links.html
```

To override the templates you can copy the whole tree to another location and point `QGIS_SERVER_API_RESOURCES_DIRECTORY` to the new location.



## 第4章 Catalog

The QGIS Server Catalog is a simple catalog that shows the list of QGIS projects served by the QGIS Server. It provides a user-friendly fully browsable website with basic mapping capabilities to quickly browse the datasets exposed through those QGIS projects.

The QGIS Server catalog uses the variables `QGIS_SERVER_LANDING_PAGE_PROJECTS_DIRECTORIES` and `QGIS_SERVER_LANDING_PAGE_PROJECTS_PG_CONNECTIONS` (see 環境変数)






図 4.1: Server Catalog project list page

You can consult the metadata associated to a project and the services that it provides. Links to those services are also given.




☒ 4.2: Server Catalog, metadata associated to a project and services (links to) that it provides.

By browsing a project, it is listed the dataset that it serves.




☒ 4.3: Browsing a dataset served by a project in the Server Catalog

Use Right click on a layer to display the attribute table associated to it.



☒ 4.4: Attribute table associated to a layer

It is possible to consult information of the elements in the map as shown in the image below:



☒ 4.5: Consulting information of a map element



## 第5章 プラグイン

### 5.1 List of plugins

Plugins can also be installed on QGIS Server.

Some plugins designed for server can be found on the official [QGIS repository](#).

Install only plugins you need for your own purpose. On QGIS server, plugins are like hooks into QGIS server, they can alter inputs or outputs of QGIS server. They can produce unexpected result if you don't know how the plugin works. Please refer to their respective documentation or the application that needs QGIS server plugins to know which plugin can be useful for you.

### 5.2 Location of plugins

By default, on Debian based systems, QGIS Server will look for plugins located in `/usr/lib/qgis/plugins`. The default value is displayed when QGIS Server is starting, in the logs. It's possible to set a custom path by defining the environment variable `QGIS_PLUGINPATH` in the web server configuration.

### 5.3 インストール

#### 5.3.1 Manually with a ZIP

As an example, to install the **HelloWorld** plugin for testing the server, using a specific folder, you first have to create a directory to hold server plugins. This will be specified in the virtual host configuration and passed on to the server through an environment variable:

```
mkdir -p /var/www/qgis-server/plugins
cd /var/www/qgis-server/plugins
wget https://github.com/elpasso/qgis-helloserver/archive/master.zip
unzip master.zip
mv qgis-helloserver-master HelloServer
```

**警告:** According to its [description](#), HelloServer plugin is designed for development and demonstration purposes. Do not keep this plugin for production if you don't need it.

### 5.3.2 With a command line tool

If you need to install and regularly upgrade plugins which are stored in the QGIS plugin repository, you may use the [QGIS-Plugin-Manager](#). It's a tool to help you manage plugins from the command line.

The installation is using pip. Installing in a virtual environment is a good practice but not required:

```
pip3 install qgis-plugin-manager
```

To upgrade the tool:

```
pip3 install --upgrade qgis-plugin-manager
```

Then, you can use the `qgis-plugin-manager` executable from the command line:

```
cd /var/www/qgis-server/plugins
qgis-plugin-manager list

QGIS server version 3.19.0
List all plugins in /var/www/qgis-server/plugins

-----
↩-----
| Folder          | Name          | Version | Experimental | QGIS_
↩min | QGIS max | Author          | Action !      |
-----
↩-----
|wfsOutputExtension |wfsOutputExtension|1.6.2      |          |3.0
|          |3Liz          |          |          |
|qgis_server_render_geojson|GeoJson Renderer |v0.4      |          |3.4
|          |Matthias Kuhn (OPENGIS.ch)|          |          |
|DataPlotly          |Data Plotly     |3.7.1     |          |3.4
|3.98          |Matteo Ghetta (Faunalia) |Upgrade to 3.8.1 |          |
-----
↩-----
```

We suggest you to read the full documentation in the [readme file](#) to know how to install or upgrade plugins with this tool.

## 5.4 HTTP サーバー構成

### 5.4.1 Apache

To be able to use server plugins, FastCGI needs to know where to look. So, we have to modify the Apache configuration file to indicate the QGIS\_PLUGINPATH environment variable to FastCGI:

```
FcgidInitialEnv QGIS_PLUGINPATH "/var/www/qgis-server/plugins"
```

Moreover, a basic HTTP authorization is necessary to play with the HelloWorld plugin previously introduced. So we have to update the Apache configuration file a last time:

```
# Needed for QGIS HelloServer plugin HTTP BASIC auth
<IfModule mod_fcgid.c>
    RewriteEngine on
    RewriteCond %{HTTP:Authorization} .
    RewriteRule .* - [E=HTTP_AUTHORIZATION:%{HTTP:Authorization}]
</IfModule>
```

それから、Apache を再起動します:

```
systemctl restart apache2
```

## 5.5 プラグインの使用方法

HelloWorld のプラグインでサーバーをテストします :

```
wget -q -O - "http://localhost/cgi-bin/qgis_mapserv.fcgi?SERVICE=HELLO"
HelloServer!
```

You can have a look at the default GetCapabilities of the QGIS server at:

```
http://localhost/cgi-bin/qgis_mapserv.fcgi?SERVICE=WMS&VERSION=1.3.0&
↳REQUEST=GetCapabilities
```



## 第6章 高度な構成

### 6.1 ログを記録する

To log requests sent to the server, you have to set the following environment variable:

- *QGIS\_SERVER\_LOG\_STDERR*

With the following variables the logging can be further customized:

- *QGIS\_SERVER\_LOG\_LEVEL*
- *QGIS\_SERVER\_LOG\_PROFILE*

### 6.2 環境変数

You can configure some aspects of QGIS Server by setting **environment variables**.

According to the HTTP server and how you run QGIS Server, there are several ways to define these variables. This is fully described in *Apache HTTP Server*.

名前	説明	Default	サービス
QGIS_OPTIONS_PATH	Specifies the path to the directory with settings. It works the same way as QGIS application <code>--optionspath</code> option. It is looking for settings file in <code>&lt;QGIS_OPTIONS_PATH&gt;/QGIS/QGIS3.ini</code> .	"	All
QGIS_PLUGINPATH	Useful if you are using Python plugins for the server, this sets the folder that is searched for Python plugins.	"	All
QGIS_PROJECT_FILE	The <code>.qgs</code> or <code>.qgz</code> project file, normally passed as a parameter in the query string (with <i>MAP</i> ), you can also set it as an environment variable (for example by using <code>mod_rewrite</code> Apache module). Note that you may also indicate a project stored in PostgreSQL, e.g. <code>postgresql://localhost:5432?sslmode=disable&amp;dbname=mydb&amp;schema=myschema&amp;project=myproject</code> .	"	All
QGIS_SERVER_API_RESOURCES_DIRECTORY	Base directory for all OGC API (such as OAPIF/WFS3) static resources (HTML templates, CSS, JS, ...)	depends on packaging	OAPIF/WFS3
QGIS_SERVER_API_WFS3_MAXLIMIT	Maximum value for limit in a OAPIF/WFS3 features request.	10000	OAPIF/WFS3
QGIS_SERVER_CACHE_DIRECTORY	Specifies the network cache directory on the filesystem.	cache in profile directory	All
QGIS_SERVER_CACHE_SIZE	Sets the network cache size in MB.	50 MB	All
QGIS_SERVER_DISABLE_GETPRINT	Prints an option at the project level to improve project read time by disabling loading of layouts. Activating this option disables the QGIS WMS GetPrint request. Set this QGIS project flag to not load layouts.	false	WMS
QGIS_SERVER_IGNORE_BADLAYERS	Bad layers are layers that cannot be loaded. The default behavior of QGIS Server is to consider the project as not available if it contains a bad layer. The default behavior can be overridden by setting this variable to 1 or true. In this case, "bad" layers will just be ignored, and the project will be considered valid and available.	false	All
QGIS_SERVER_LANDING_PAGE_PREFIX	Prefix path component of the landing page base URL	""	All
QGIS_SERVER_LANDING_PAGE_PROJECTS_DIRECTORIES	Directories used by the landing page service to find <code>.qgs</code> and <code>.qgz</code> projects	""	All
QGIS_SERVER_LANDING_PAGE_PROJECTS_PG_CONNECTIONS	PostgreSQL connection strings used by the landing page service to find projects	""	All
QGIS_SERVER_LOG_FILE	Specify path and filename. Make sure that server has proper permissions for writing to file. File should be created automati	"	All

## 6.3 Settings summary

When QGIS Server is starting, you have a summary of all configurable parameters thanks to environment variables. Moreover, the value currently used and the origin is also displayed.

For example with spawn-fcgi:

```
export QGIS_OPTIONS_PATH=/home/user/.local/share/QGIS/QGIS3/profiles/default/
export QGIS_SERVER_LOG_STDERR=1
export QGIS_SERVER_LOG_LEVEL=2
spawn-fcgi -f /usr/lib/cgi-bin/qgis_mapserv.fcgi -s /tmp/qgisserver.sock -U www-data -
↳G www-data -n

QGIS Server Settings:

- QGIS_OPTIONS_PATH / '' (Override the default path for user configuration): '/
↳home/user/.local/share/QGIS/QGIS3/profiles/default/' (read from ENVIRONMENT_
↳VARIABLE)

- QGIS_SERVER_PARALLEL_RENDERING / '/qgis/parallel_rendering' (Activate/Deactivate
↳parallel rendering for WMS getMap request): 'true' (read from INI_FILE)

- QGIS_SERVER_MAX_THREADS / '/qgis/max_threads' (Number of threads to use when
↳parallel rendering is activated): '4' (read from INI_FILE)

- QGIS_SERVER_LOG_LEVEL / '' (Log level): '2' (read from ENVIRONMENT_VARIABLE)

- QGIS_SERVER_LOG_STDERR / '' (Activate/Deactivate logging to stderr): '1' (read
↳from ENVIRONMENT_VARIABLE)

- QGIS_PROJECT_FILE / '' (QGIS project file): '' (read from DEFAULT_VALUE)

- MAX_CACHE_LAYERS / '' (Specify the maximum number of cached layers): '100' (read
↳from DEFAULT_VALUE)

- QGIS_SERVER_CACHE_DIRECTORY / '/cache/directory' (Specify the cache directory):
↳'/root/.local/share/QGIS/QGIS3/profiles/default/cache' (read from DEFAULT_VALUE)

- QGIS_SERVER_CACHE_SIZE / '/cache/size' (Specify the cache size): '52428800'
↳(read from INI_FILE)

Ini file used to initialize settings: /home/user/.local/share/QGIS/QGIS3/profiles/
↳default/QGIS/QGIS3.ini
```

In this particular case, we know that **QGIS\_SERVER\_MAX\_THREADS** and **QGIS\_SERVER\_PARALLEL\_RENDERING** values are read from the ini file found in **QGIS\_OPTIONS\_PATH** directory (which is defined through an environment variable). The correspond-

ing entries in the ini file are `/qgis/max_threads` and `/qgis/parallel_rendering` and their values are `true` and `4` threads.

## 6.4 サービスファイルへの接続

PostgreSQL のサービス・ファイルの Apache が認識できるようにするために ( PG サービスファイル セクションを参照 ) \*.conf ファイルのようなを見て、確認する必要があります:

```
SetEnv PGSERVICEFILE /home/web/.pg_service.conf

<Directory "/home/web/apps2/bin/">
    AllowOverride None
    .....

```

## 6.5 お使いの Linux サーバーにフォントを追加

他のマシン上のデフォルトでは存在しないかもしれないフォントを指す QGIS プロジェクトを使用するかもしれないことに注意してください。これは、プロジェクトを共有する場合 ( フォントがターゲットマシン上に存在しない場合 ) それは他のマシン上で異なって見える可能性があることを意味します。

これが起こらないようにするために、単にターゲットマシン上で不足しているフォントをインストールする必要があります。デスクトップシステム上でこれを行うのは通常は自明です ( フォントをダブルクリック )

Linux に対しては、デスクトップ環境をインストールしていない ( または、コマンドラインを好む ) 場合、する必要があります :

- Debian のベースのシステム:

```
sudo su
mkdir -p /usr/local/share/fonts/truetype/myfonts && cd /usr/local/share/fonts/
->truetype/myfonts

# copy the fonts from their location
cp /fonts_location/* .

chown root *
cd .. && fc-cache -f -v

```

- Fedora のベースのシステム:

```
sudo su
mkdir /usr/share/fonts/myfonts && cd /usr/share/fonts/myfonts

# copy the fonts from their location
cp /fonts_location/* .

```

(次のページに続く)

(前のページからの続き)

```
chown root *  
cd .. && fc-cache -f -v
```



## 第7章 Development Server

A production installation and deployment of QGIS Server usually involves setting up a web server component (e.g. Apache or Nginx) that can forward the HTTP requests coming from the clients to the QGIS Server FastCGI binary application.

If you want to quickly test QGIS Server on your local machine without configuring and installing a full web server stack you can use the QGIS Development Standalone server.

This is an independent application that provides a very simple web server ready to serve your project files.

**警告:** The Standalone Development Server has not been developed with the purpose of being used in production, it was not checked for security vulnerabilities or for other stress conditions that normally will occur on a publicly exposed server.

To launch the server:

```
$ qgis_mapserver
```

The default port the Development Server listens to is 8000. Example output:

```
QGIS Development Server listening on http://localhost:8000
CTRL+C to exit
127.0.0.1 [lun gen 20 15:16:41 2020] 5140 103ms "GET /wfs3/?MAP=/tests/testdata/qgis_
↪server/test_project.qgs HTTP/1.1" 200
127.0.0.1 [lun gen 20 15:16:41 2020] 3298 2ms "GET /wfs3/static/jsonFormatter.min.js_
↪HTTP/1.1" 200
127.0.0.1 [lun gen 20 15:16:41 2020] 1678 3ms "GET /wfs3/static/jsonFormatter.min.css_
↪HTTP/1.1" 200
127.0.0.1 [lun gen 20 15:16:41 2020] 1310 5ms "GET /wfs3/static/style.css HTTP/1.1"
↪200
127.0.0.1 [lun gen 20 15:16:43 2020] 4285 13ms "GET /wfs3/collections?MAP=/tests/
↪testdata/qgis_server/test_project.qgs HTTP/1.1" 200
```

The server has a few options that can be passed as command line arguments. You can see them all by invoking the server with `-h`.

```
Usage: qgis_mapserver [options] [address:port]
QGIS Development Server
```

(次のページに続く)

Options:

```
-h, --help           Displays this help.
-v, --version        Displays version information.
-l <logLevel>        Sets log level (default: 0)
                     0: INFO
                     1: WARNING
                     2: CRITICAL
-p <projectPath>     Path to a QGIS project file (*.qgs or *.qgz),
                     if specified it will override the query string MAP argument
                     and the QGIS_PROJECT_FILE environment variable
```

Arguments:

```
addressAndPort       Listen to address and port (default: "localhost:8000")
                     address and port can also be specified with the environment
                     variables QGIS_SERVER_ADDRESS and QGIS_SERVER_PORT
```

## 第8章 コンテナ化された配備

コンテナ化されたアプリケーションを使用するには、最も単純なもの（単純な Docker イメージ）から高度なもの（Kubernetes など）まで、さまざまな方法があります。

---

注釈: この種類の配備では、[docker アプリケーション](#) をインストールして実行する必要があります。この [チュートリアル](#) を確認してください。

---

---

ヒント: Docker は、パッケージ化されたアプリケーション（別名イメージ）を実行します。これは、ビルドするソース（Dockerfile およびリソース）として取得するか、レジストリ（プライベートまたはパブリック）から既にビルドできます。

---

---

注釈: QGIS Debian-Ubuntu package downloads need a valid gpg authentication key. Please refer to the [installation pages](#) to update the following Dockerfile.

---

### 8.1 Simple docker images

Docker イメージがパブリックレジストリに存在しないため、ビルドする必要があります。そのためには、ディレクトリ `qgis-server` をそのディレクトリ内に作成します。

- create a file Dockerfile with this content:

```
FROM debian:bullseye-slim

ENV LANG=en_EN.UTF-8

RUN apt-get update \
    && apt-get install --no-install-recommends --no-install-suggests --allow-
↪unauthenticated -y \
    gnupg \
    ca-certificates \
    wget \
    locales \
```

(次のページに続く)

```
&& localedef -i en_US -f UTF-8 en_US.UTF-8 \  
# Add the current key for package downloading  
# Please refer to QGIS install documentation (https://www.qgis.org/fr/site/forusers/alldownloads.html#debian-ubuntu)  
-> && mkdir -m755 -p /etc/apt/keyrings \  
&& wget -O /etc/apt/keyrings/qgis-archive-keyring.gpg https://download.qgis.org/downloads/qgis-archive-keyring.gpg \  
# Add repository for latest version of qgis-server  
# Please refer to QGIS repositories documentation if you want other version.  
-> (https://qgis.org/en/site/forusers/alldownloads.html#repositories)  
&& echo "deb [signed-by=/etc/apt/keyrings/qgis-archive-keyring.gpg] https://qgis.org/debian bullseye main" | tee /etc/apt/sources.list.d/qgis.list \  
-> && apt-get update \  
&& apt-get install --no-install-recommends --no-install-suggests --allow-unauthenticated -y \  
    qgis-server \  
    spawn-fcgi \  
    xauth \  
    xvfb \  
&& apt-get remove --purge -y \  
    gnupg \  
    wget \  
&& rm -rf /var/lib/apt/lists/*  
  
RUN useradd -m qgis  
  
ENV TINI_VERSION v0.19.0  
ADD https://github.com/krallin/tini/releases/download/\${TINI\_VERSION}/tini /tini  
RUN chmod +x /tini  
  
ENV QGIS_PREFIX_PATH /usr  
ENV QGIS_SERVER_LOG_STDERR 1  
ENV QGIS_SERVER_LOG_LEVEL 2  
  
COPY cmd.sh /home/qgis/cmd.sh  
RUN chmod -R 777 /home/qgis/cmd.sh  
RUN chown qgis:qgis /home/qgis/cmd.sh  
  
USER qgis  
WORKDIR /home/qgis  
  
ENTRYPOINT ["/tini", "--"]  
  
CMD ["/home/qgis/cmd.sh"]
```

- create a file `cmd.sh` with this content:

```
#!/bin/bash

[[ $DEBUG == "1" ]] && env

exec /usr/bin/xvfb-run --auto-servernum --server-num=1 /usr/bin/spawn-fcgi -p 5555 -n_
↪-d /home/qgis -- /usr/lib/cgi-bin/qgis_mapserv.fcgi
```

- build the image with:

```
docker build -f Dockerfile -t qgis-server ./
```

### 8.1.1 First run

To run the server you will need a QGIS project file. You can use one of yours or pick [this sample](#).

これを行うには、ディレクトリ `qgis-server` 内にディレクトリ `data` を作成し、その中にファイルをコピーします。以下の説明に準拠するため、名前を `osm.qgs` に変更します。

---

注釈: You may need to add advertised URLs under the *QGIS Server* tab of the *Project Properties* if the GetCapabilities are broken. For example if your server is exposed on port 8080, you will put this for advertised URL `http://localhost:8080/qgis-server/`. More information available in section *Configure your project* and subsequent.

---

Now, you can run the server with:

```
docker network create qgis
docker run -d --rm --name qgis-server --net=qgis --hostname=qgis-server \
-v $(pwd)/data:/data:ro -p 5555:5555 \
-e "QGIS_PROJECT_FILE=/data/osm.qgs" \
qgis-server
```

Options used:

- **-d**: run in the background
- **--rm**: remove the container when it is stopped
- **--name**: name of the container to be created
- **--net**: (previously created) sub network
- **--hostname**: container hostname, for later referencing
- **-v**: local data directory to be mounted in the container
- **-p**: host/container port mapping

- `-e`: environment variable to be used in the container

To check, type `docker ps | grep qgis-server` and you should see a line with **qgis-server**:

CONTAINER ID	IMAGE	COMMAND	CREATED	STATUS
<code>↔</code> PORTS		NAMES		
<code>4de8192da76e</code>	<code>qgis-server</code>	<code>"/tini -- /home/qgis..."</code>	<code>3 seconds ago</code>	<code>Up 2 seconds</code>
<code>↔0.0.0.0:5555-&gt;5555/tcp</code>		<code>qgis-server</code>		

### 8.1.2 Usable sample

As the server is only accepting fastcgi connections, you need an HTTP server that handles this protocol. To do so we have to create a simple Nginx configuration file and start a Nginx image.

Create a file `nginx.conf` in the current directory with this content:

```
server {
    listen 80;
    server_name _;
    location / {
        root /usr/share/nginx/html;
        index index.html index.htm;
    }
    location /qgis-server {
        proxy_buffers 16 16k;
        proxy_buffer_size 16k;
        gzip off;
        include fastcgi_params;
        fastcgi_pass qgis-server:5555;
    }
}
```

And type this command:

```
docker run -d --rm --name nginx --net=qgis --hostname=nginx \
    -v $(pwd)/nginx.conf:/etc/nginx/conf.d/default.conf:ro -p 8080:80 \
    nginx:1.13
```

To check capabilities availability, type in a browser <http://localhost:8080/qgis-server/?SERVICE=WMS&VERSION=1.3.0&REQUEST=GetCapabilities>

### 8.1.3 Cleanup

To cleanup the running images, type:

```
docker stop qgis-server nginx
```

## 8.2 Docker stacks

The previous method is scriptable, but not easily packageable nor standardized or easily manageable.

Docker イメージセットを操作するには、オーケストレーターが管理する Docker スタックを使用できます。スタックでは、イメージは同じプライベートネットワークで動作しており、スタック全体を開始/停止したり、スタックを他のワーカーに配備したりできます。たとえば、Swarm、Kubernetes、Mesos など、多くのオーケストレーターがいます。

In the following, we will present simple configurations for testing purposes. They are not suitable for production.

### 8.2.1 Swarm/docker-compose

Docker に独自のオーケストレーター Swarm が追加されました ( docker-compose ファイルと互換性があります )、`有効にする<<https://docs.docker.com/get-started/orchestration/#enable-docker-swarm>>` 必要があります ( Mac バージョンは Linux でも動作します )、

#### Stack description

Now that you have Swarm working, create the service file (see [Deploy to Swarm](#)) `qgis-stack.yaml`:

```
version: '3.7'

services:
  qgis-server:
    # Should use version with utf-8 locale support:
    image: qgis-server:latest
    volumes:
      - REPLACE_WITH_FULL_PATH/data:/data:ro
    environment:
      - LANG=en_EN.UTF-8
      - QGIS_PROJECT_FILE=/data/osm.qgs
      - QGIS_SERVER_LOG_LEVEL=0 # INFO (log all requests)
      - DEBUG=1 # display env before spawning QGIS Server

  nginx:
    image: nginx:1.13
```

(次のページに続く)

(前のページからの続き)

```
ports:
- 8080:80
volumes:
- REPLACE_WITH_FULL_PATH/nginx.conf:/etc/nginx/conf.d/default.conf:ro
depends_on:
- qgis-server
```

To deploy (or update) the stack, type:

```
docker stack deploy -c qgis-stack.yaml qgis-stack
```

Check the stack deployment status until you obtain **1/1** in the **replicas** column:

```
docker stack services qgis-stack
```

Something like:

ID	NAME	MODE	REPLICAS	IMAGE
	PORTS			
gmx7ewlvwsqt	qgis_nginx	replicated	1/1	
↪ nginx:1.13	*:8080->80/tcp			
10v2e7c143u3	qgis_qgis-server	replicated	1/1	qgis-
↪ server:latest				

To check WMS capabilities, type in a web browser <http://localhost:8080/qgis-server/?SERVICE=WMS&VERSION=1.3.0&REQUEST=GetCapabilities>

### Cleanup

To cleanup, type:

```
docker stack rm qgis-stack
```

## 8.2.2 Kubernetes

### インストール

If you have a **Docker Desktop** installation, using Kubernetes (aka k8s) is pretty straight forward: [enable k8s](#).

If not, follow the [minikube tutorial](#) or [microk8s for Ubuntu](#).

As Kubernetes installation can be really complex, we will only focus on aspects used by this demo. For further / deeper information, check the [official documentation](#).

## microk8s

microk8s では追加の手順が必要です。Kubernetes で作成されたイメージを検出するには、レジストリを有効にして qgis-server イメージにタグを付ける必要があります。

First, enable the registry:

```
microk8s enable dashboard dns registry
```

Then, tag and push the image to your newly created registry:

```
docker tag qgis-server 127.0.0.1:32000/qgis-server && docker push 127.0.0.1:32000/  
↔qgis-server
```

Finally, add or complete the `/etc/docker/daemon.json` to have your registry **127.0.0.1:32000** listed in the **insecure-registries** field:

```
{  
  "insecure-registries": ["127.0.0.1:32000"]  
}
```

## Creating manifests

Kubernetes は、yaml マニフェストにデプロイするオブジェクトを記述します。さまざまな種類がありますが、デプロイメント（ポッドを処理する、つまり Docker イメージ）とサービスのみを使用して、デプロイメントを内部または外部の目的に公開します。

## Deployment manifests

Create a file `deployments.yaml` with this content:

```
apiVersion: apps/v1  
kind: Deployment  
metadata:  
  name: qgis-server  
  namespace: default  
spec:  
  replicas: 1  
  selector:  
    matchLabels:  
      myLabel: qgis-server  
  template:  
    metadata:  
      labels:  
        myLabel: qgis-server
```

(次のページに続く)

```
spec:
  containers:
    - name: qgis-server
      image: localhost:32000/qgis-server:latest
      imagePullPolicy: IfNotPresent
      env:
        - name: LANG
          value: en_EN.UTF-8
        - name: QGIS_PROJECT_FILE
          value: /data/osm.qgs
        - name: QGIS_SERVER_LOG_LEVEL
          value: "0"
        - name: DEBUG
          value: "1"
      ports:
        - containerPort: 5555
      volumeMounts:
        - name: qgis-data
          mountPath: /data/
  volumes:
    - name: qgis-data
      hostPath:
        path: REPLACE_WITH_FULL_PATH/data
```

---

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: qgis-nginx
  namespace: default
spec:
  replicas: 1
  selector:
    matchLabels:
      myLabel: qgis-nginx
  template:
    metadata:
      labels:
        myLabel: qgis-nginx
    spec:
      containers:
        - name: qgis-nginx
          image: nginx:1.13
          ports:
            - containerPort: 80
```

(次のページに続く)

(前のページからの続き)

```
  volumeMounts:
    - name: nginx-conf
      mountPath: /etc/nginx/conf.d/default.conf
  volumes:
    - name: nginx-conf
      hostPath:
        path: REPLACE_WITH_FULL_PATH/nginx.conf
```

## Service manifests

Create a file `services.yaml` with this content:

```
apiVersion: v1
kind: Service
metadata:
  name: qgis-server
  namespace: default
spec:
  type: ClusterIP
  selector:
    myLabel: qgis-server
  ports:
    - port: 5555
      targetPort: 5555
---
apiVersion: v1
kind: Service
metadata:
  name: qgis-nginx
  namespace: default
spec:
  type: NodePort
  selector:
    myLabel: qgis-nginx
  ports:
    - port: 80
      targetPort: 80
      nodePort: 30080
```

### Deploying manifests

To deploy the images and services in Kubernetes, one can use the dashboard (click on the + on the upper right) or the command line.

注釈: When using the command line with `microk8s` you will have to prefix each command with `microk8s`.

To deploy or update your manifests:

```
kubectl apply -k ./
```

To check what is currently deployed:

```
kubectl get pods,services,deployment
```

You should obtain something like:

NAME	READY	STATUS	RESTARTS	AGE
pod/qgis-nginx-54845ff6f6-8skp9	1/1	Running	0	27m
pod/qgis-server-75df8ddd89-c7t7s	1/1	Running	0	27m

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	
↪AGE					
service/Kubernetes	ClusterIP	10.152.183.1	<none>	443/TCP	↵
↪5h51m					
service/qgis-exec-server	ClusterIP	10.152.183.218	<none>	5555/TCP	↵
↪35m					
service/qgis-nginx	NodePort	10.152.183.234	<none>	80:30080/TCP	↵
↪27m					
service/qgis-server	ClusterIP	10.152.183.132	<none>	5555/TCP	↵
↪27m					

NAME	READY	UP-TO-DATE	AVAILABLE	AGE
deployment.apps/qgis-nginx	1/1	1	1	27m
deployment.apps/qgis-server	1/1	1	1	27m

To read nginx/qgis logs, type:

```
kubectl logs -f POD_NAME
```

To check WMS capabilities, type in a web browser <http://localhost:30080/qgis-server/?SERVICE=WMS&VERSION=1.3.0&REQUEST=GetCapabilities>

## Cleanup

To clean up, type:

```
kubectl delete -n default service/qgis-server service/qgis-nginx deployment/qgis-  
↩️ nginx deployment/qgis-server
```

## 8.3 Cloud deployment

Managing your own cluster of servers to handle the deployment of containerized applications, is a complex job. You have to handle multiple issues, such as hardware, bandwidth and security at different levels.

Cloud deployment solutions can be a good alternative when you do not want to focus on infrastructure management.

A cloud deployment may use proprietary mechanisms, but they are also compatible with the stages explained previously (*docker images* and *stack management*).

### 8.3.1 AWS usecase

With Amazon AWS, through [ECS \(Elastic Container Service\)](#) functionalities, you can use docker-compose or Kubernetes compatible wrappers to manage your stack. You will have to create an [image registry](#) for your custom images to be accessible.

To use docker-compose alike functionalities, you need to install the [ecs-cli](#) client and have [proper permissions / roles](#). Then, with the help of the [ecs-cli compose](#) commands, you can reuse the [stack description](#).

To use Kubernetes, you can use the AWS web console or the command line tool [eksctl](#) and have the [proper permissions / roles](#). Then with a well configured kubectl environment, you can reuse the [Kubernetes manifests](#).



## 第9章 Frequently Asked Question

- *What are the differences between QGIS Desktop and QGIS Server?*

QGIS Desktop has a graphical user interface and allows you to create and modify maps. QGIS Server is a server application serving your QGIS project files to end user applications via OGC web services like WMS, WFS, etc..

- *What is OGC?*

The OGC (Open Geospatial Consortium) is an international not for profit organization committed to making quality open standards for the global geospatial community.

- *Name some other web mapping servers?*

ArcGIS server, Geoserver, Mapserver, Mapnik etc.

- *How to compare QGIS server to other web mapping servers? (2021/01/01)*

Features	QGIS Server	GeoServer	ArcGIS Server
Since	2006	2001	1999
Licence	GPL	GPL	commercial
Commercial support	Multiple companies	Multiple companies	ESRI and its vendors network
Technology	C++/python	Java	C++
Tile cache	yes	yes (via GeoWebCache)	yes
3D	No	No	Yes
Querying	FES (2.0) and OGC (1.0) filters	CQL and OGC filters	OGC filters
Report generation	yes	yes	yes
Server administration	yes via third parties (LizMap, QWC2, etc.)	web + API REST	web + API REST
GIS project Layer/symbology edition	complete via dedicated GUI	simple via web interface	complete via dedicated GUI

- *What are the OGC specification versions implemented in QGIS server compared to other web mapping servers? (2021/01/01)*

OGC standards	QGIS Server	GeoServer	ArcGIS Server
WMS (Web Map Service)	1.3.0 - 1.1.1	1.3.0 - 1.1.1	1.3.0 - 1.1.1
WFS (Web Feature Service)	1.1.0 - 1.0.0	2.0.0 - 1.0.0	2.0.0 - 1.0.0
OAPIF (aka WFS3)	1.0.0	no	no
WMTS (Web Map Tile Service)	1.0.0	1.0.0	1.0.0
WCS (Web Coverage Service)	1.0.0	2.0.1 - 1.0.0	2.0.1 - 1.0.0
WPS (Web Processing Service)	no	1.0.0	1.0.0
CSW (Catalogue Service for the Web)	no	2.0.2	no
SLD (Styled Layer Descriptor)	yes	yes	yes

- *What is a tile cache?*

Maps are often static. As most mapping clients render WMS (Web Map Service) data every time they are queried, this can result in unnecessary processing and increased wait times.

The tile cache optimizes this experience by saving (caching) map images, or tiles, as they are requested, in effect acting as a proxy between client (such as OpenLayers or Google Maps) and server (any WMS-compliant server). As new maps and tiles are requested, QGIS server intercepts these calls and returns pre-rendered tiles if stored, or calls the QGIS engine to render new tiles as necessary. Thus, once tiles are stored, the speed of map rendering increases by many times, creating a much improved user experience.

- *What is PostgreSQL?*

PostgreSQL is a powerful, open source object-relational database companion for QGIS.

- *What is PostGIS?*

PostGIS is a spatial database extender for PostgreSQL object-relational database. It adds support for geographic objects allowing location queries to be run in SQL.

- To be continued...